

Oracle® WebCenter Sites

Property Files Reference

11g Release 1 (11.1.1)

April 2012

Oracle® WebCenter Sites: Property Files Reference, 11g Release 1 (11.1.1)

Copyright © 2012 Oracle and/or its affiliates. All rights reserved.

Primary Author: Tatiana Kolubayev

Contributor: Hareesh Kadlabalu, Ravi Khanuja, Vipin Kumar, Yogesh Khubchandani, Cory Lum

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle America, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Table of Contents

About This Guide	7
Audience	7
How This Guide Is Organized	7
Related Documents	8
Conventions	8
Third-Party Libraries	8
Introduction	9
Overview of the Property Editor	10
Starting the Property Editor	10
Setting Properties	10
Adding Properties	11
Deleting Properties	12

Part 1. Oracle WebCenter Sites

assetframework.ini	15
User Defined Tab	15
batch.ini	16
Configuration Tab	17
Debug Tab	18
Results Tab	18
Security Tab	18
User Defined Tab	18
catalog.ini	19
Catalog Tab	19
User Defined Tab	19
commons-logging.properties	20
AsyncLog Tab	21

Factory Tab	21
Loggers Tab	22
Traditional Log Tab	31
User Defined Tab	32
CSPortletRequest.properties	34
User Defined Tab	34
dir.ini	35
Attribute Names Tab	36
Compatibility Tab	38
Global Data Tab	39
Interface Implementations Tab	40
JNDI SPI Env. Tab	42
Naming Syntax Tab	44
Schema Defaults Tab	46
Search Controls Tab	48
User Defined Tab	48
fatwire_settings.properties	49
User Defined Tab	49
futuretense.ini	50
App Server Tab	51
Authentication Tab	52
Basic Tab	55
Blob Server Tab	58
Cluster Tab	60
Compatibility Tab	61
Content Tables Tab	64
Database Tab	65
Debug Tab	71
Email Tab	72
Export/Mirror Tab	74
JSP Tab	76
Misc Tab	78
Page Cache Tab	82
ResultSet Cache Tab	86
Satellite Server Tab	90
Search Tab	92
User Defined Tab	92
futuretense_xcel.ini	99
Analytics Tab	100
Asset Default Tab	101
Authorization Tab	104
Debug Tab	110
Directories Tab	111
Element Override Tab	113
Preference Tab	114

Publishing Tab	117
Transformer Tab	122
xcelerate Tab	124
User Management Tab	129
User Defined Tab	132
gator.ini	134
Gator Tab	134
User Defined Tab	138
log4j.properties	139
logging.ini (Deprecated)	140
Global Data Tab	140
Message Resources Tab	141
User Defined Tab	141
omii.ini	142
omproduct.ini	142
satellite.properties	143
Caching Tab	144
Configuration Tab	146
Remote Host Tab	148
Sessions Tab	149
Compatibility Tab	151
User Defined Tab	152
ServletRequest.properties	153
Request Encoding Tab	154
Request Threshold Tab	154
URI Assembler Tab	155
User Defined Tab	157
visitor.ini	158
Visitor Data Tab	158
User Defined Tab	160

Part 2. Oracle WebCenter Sites Applications

Oracle WebCenter Sites: Analytics Properties	163
Oracle WebCenter Sites: Engage Properties	163
Oracle WebCenter Sites: Satellite Server Property Files	163

Part 3. Third-Party Libraries and Applications

HTTP Client Access	166
Apache Commons HttpClient	166
Integration with WebCenter Sites	166
Implementation	168
HTTPClient Parameters and WebCenter Sites Properties	169
Index	177
Index of Properties	179
New Properties in Oracle WebCenter Sites 11gR1	191
Deprecated Properties	193

About This Guide

This guide contains information about Oracle WebCenter Sites property files and their properties. They are used to specify operating parameters for Oracle WebCenter Sites and its applications.

Applications discussed in this guide are former FatWire products. Naming conventions are the following:

- *Oracle WebCenter Sites* is the current name of the application previously known as *FatWire Content Server*. In this guide, *Oracle WebCenter Sites* is also called *WebCenter Sites*.
- *Oracle WebCenter Sites: Web Experience Management Framework* is the current name of the environment previously known as *FatWire Web Experience Management Framework*. In this guide, *Oracle WebCenter Sites: Web Experience Management Framework* environment is also called *WEM Framework*.
- *Oracle WebCenter Sites: Analytics* is the current name of the application previously known as *FatWire Analytics*. In this guide, *Oracle WebCenter Sites: Analytics* is also called *Analytics*.
- *Oracle WebCenter Sites: Engage* is the current name of the application previously known as *FatWire Engage*. In this guide, *Oracle WebCenter Sites: Engage* is also called *Engage*.
- *Oracle WebCenter Sites: Satellite Server* is the current name of the application previously known as *FatWire Satellite Server*. In this guide, *Oracle WebCenter Sites: Satellite Server* is also called *Satellite Server*.

Audience

This guide is written for WebCenter Sites installation engineers, developers, and administrators of WebCenter Sites systems.

How This Guide Is Organized

The introductory section explains the importance of using the Property Editor to modify property files and provides instructions on using the Property Editor.

[Part 1, “Oracle WebCenter Sites”](#) covers properties for WebCenter Sites and its page caching application Satellite Server.

[Part 2, “Oracle WebCenter Sites Applications”](#) covers the property files of the WebCenter Sites: Engage application and remotely installed Satellite Server.

[Part 3, “Third-Party Libraries and Applications”](#) explains how WebCenter Sites integrates with third-party libraries.

At the end of this reference are several indexes to help readers find topics and properties in this guide and to quickly identify new and deprecated properties.

Related Documents

For more information, see the following documents:

- *Oracle WebCenter Sites Developer’s Guide*
- *Oracle WebCenter Sites Administrator’s Guide*
- *Oracle WebCenter Sites Tag Reference*

Conventions

The following text conventions are used in this guide:

- **Boldface** type indicates graphical user interface elements that you select.
- *Italic* type indicates book titles, emphasis, or variables for which you supply particular values.
- `Monospace` type indicates file names, URLs, sample code, or text that appears on the screen.
- **Monospace bold** type indicates a command.

Third-Party Libraries

Oracle WebCenter Sites 11gR1 and its applications include third-party libraries. For additional information, see *Oracle WebCenter Sites 11gR1: Third-Party Licenses*.

Introduction

Many of your configuration tasks for Oracle WebCenter Sites and its applications require you to set or modify values for properties that are specified in property files. These files have either the `.ini` or `.properties` suffix.

A set of property files, along with the “Property Editor” utility, is provided with WebCenter Sites. At least one property file is associated with each of the WebCenter Sites applications, such as WebCenter Sites: Analytics, WebCenter Sites: Engage, and WebCenter Sites: Satellite Server.

This introduction describes the Property Editor and summarizes the property files that are presented in the rest of this reference.

This introduction contains the following sections:

- [Overview of the Property Editor](#)
- [Starting the Property Editor](#)
- [Setting Properties](#)
- [Adding Properties](#)
- [Deleting Properties](#)

Overview of the Property Editor

The Property Editor is used to set the values of properties in Oracle WebCenter Sites' property files. We recommend that you always use the Property Editor to set values, because using other editors can create problems. For example, the JumpStart Kit renames property files; launching the Property Editor ensures that the correct file will be displayed for modification. The Property Editor is also capable of encrypting password fields; modifying the fields outside the Property Editor can corrupt the property values. In addition, the Property Editor ensures that the files are correctly formatted; specifically, the correct property separator characters are used. Furthermore, the Property Editor organizes properties by function on tabs, and provides descriptive information about the properties, as well as default or possible values.

Starting the Property Editor

Execute the following scripts at the command line prompt or in a UNIX shell:


- Windows: `propeditor.bat`, typically located in `<cs_install_dir>/`
- Solaris: `propeditor.sh`, typically located in `$HOME/<cs_install_dir>`

Setting Properties

To set properties for WebCenter Sites and its applications:

1. Start the Property Editor, as described in [“Starting the Property Editor.”](#)
2. Select **File > Open**.
3. Browse to the property file that you need to modify and then select it.

The Property Editor opens the file. For example, this is what the `futuretense.ini` file looks like when it is first opened in the Property Editor:



- The tabs (on the left-hand side) group properties by function.
 - The **Items** pane lists the properties in the selected tab.
 - The **Value** pane lists the current value for the selected property, a brief description of the property, and acceptable values for the property.
4. Select the tab that represents the functional group that contains the property that you want to configure.
The Property Editor displays the properties from that tab in the **Items** pane.
 5. Select the property from the **Items** pane.
The Property Editor displays the value that is currently set for that property value and a provides a brief description of the property in the **Values** pane.
 6. In the **Values** pane, enter the value for the property in the text field at the top.
 7. Click **Accept**.
 8. Repeat [steps 4](#) through [7](#) for each property that you want to configure.
 9. When you are finished, select **File > Save**.
 10. Select **File > Close**.
 11. Stop and restart the application server so the new values can take effect.


Adding Properties

Some configuration tasks require you to add new, custom properties for your system. For example, when you implement resultset caching, you can create up to three properties for any WebCenter Sites database table for which you want to set caching values. (For information about resultset caching, see the *WebCenter Sites Developer's Guide*.)

To add a property to the WebCenter Sites database:

1. Start the Property Editor, as described in [“Starting the Property Editor”](#) on page 10.
2. Select **File > Open**.
3. Browse to the property file in which you need to add a property.
4. (Optional) Select the **User Defined** tab. (This step is optional because any property that you create is displayed on the **User Defined** tab the next time you open this property file in the Property Editor no matter which tab you select.)
5. In the **Values** pane, just under the text entry field, click **New**.

The Property Editor displays the **WebCenter Sites Properties** dialog box:



6. Click in the **Name** field and enter the name of the new property.

7. Click in the **Value** field and enter the value for the new property.
8. Click **OK**.

The new property appears in the **Items** pane and the value appears in the **Values** pane.

Note

If you did not select the **User Defined** tab in [step 4](#), the new property might appear on the tab that was selected when you clicked **New** in [step 5](#). This is temporary. The next time that you open this `ini` file in the Property Editor, the property is displayed on the **User Defined** tab.

9. Select **File > Save**.

Deleting Properties

It is unlikely that you will ever have to delete a property. However, if you do have to delete a property, refer to the steps below.

To delete a property:

Caution

Never delete a required property.

1. Start the Property Editor. (See [“Starting the Property Editor,”](#) above.)
2. Select **File > Open**.
3. Browse to the property file that you need to modify by deleting a property and select it.
4. Select the tab that represents the functional group that holds the property that you want to delete.
5. Take note of the current value for this property just in case you need to restore it for any reason.
6. In the **Values** pane, just under the text entry field, click **Delete**.
7. The Property Editor displays a confirmation message. Click **Yes**.
The property is deleted from the property file.
8. Select **File > Save**.

Part 1

Oracle WebCenter Sites

This part lists the property files that are installed and used by WebCenter Sites, including its user manager plug-ins and co-resident Satellite Server. The Property Editor is used to set properties in WebCenter Sites property files.

This part contains information about the following property files:

- [assetframework.ini](#)
- [batch.ini](#)
- [catalog.ini](#)
- [commons-logging.properties](#)
- [CSPortletRequest.properties](#)
- [dir.ini](#)
- [futuretense.ini](#)
- [futuretense_xcel.ini](#)
- [gator.ini](#)
- [logging.ini \(Deprecated\)](#)
- [log4j.properties](#)
- [omii.ini](#)
- [omproduct.ini](#)
- [satellite.properties](#)
- [ServletRequest.properties](#)
- [visitor.ini](#)

assetframework.ini

The `assetframework.ini` file holds properties that determine the storage locations of files that hold information about flex asset history and publishing.

This file has a single tab, named “User Defined,” in the Property Editor.

assetframework.ini: User Defined Tab

Properties `assetframework.ini`: User Defined Tab

Property	Description
<code>afk.historydata</code>	Specifies the directory that holds history data. Default value: <code>c:/futuretense/history/</code>
<code>afk.publishdata</code>	Specifies the directory that holds publish data. Default value: <code>c:/futuretense/publish/</code>

batch.ini

The `batch.ini` file provides configuration information for batch processes, which are used in the background by WebCenter Sites for various reasons (publishing, for example).

Properties in `batch.ini` are organized by function on the following tabs in the Property Editor:

- [Configuration Tab](#)
- [Debug Tab](#)
- [Results Tab](#)
- [Security Tab](#)
- [User Defined Tab](#)

batch.ini: Configuration Tab

The **Configuration** tab holds properties that are used to configure settings for the threads that are used by the batch processes.

Properties in `batch.ini`: **Configuration Tab**

Property	Description
<code>thread.count</code>	<p>Specifies the number of dispatcher threads to allocate and manage in the pool.</p> <p>Default value: 32</p>
<code>thread.growcache</code>	<p>Specifies whether additional dispatcher threads (in excess of the number specified by <code>thread.count</code>) can be allocated to the pool if they are needed.</p> <p>Possible values: <code>true</code> <code>false</code></p> <p>Default value: <code>false</code></p>
<code>thread.idle</code>	<p>Applies only when <code>thread.growcache</code> is set to <code>true</code>.</p> <p>Specifies the number of seconds a dispatcher thread can remain idle before it is released by the pool.</p> <p>Default value: 10</p>
<code>thread.wait</code>	<p>Applies only when <code>thread.growcache</code> is set to <code>false</code>.</p> <p>Specifies the number of seconds that a batch process waits for a free dispatcher thread before it reports an error because it cannot complete its task.</p> <p>Default value: 15</p>

batch.ini: Debug TabProperties in batch.ini: **Debug Tab**

Property	Description
debug	Specifies whether debugging for batch processes is enabled or disabled. If you set this value to <code>true</code> , messages about the status of batch processes are written to the WebCenter Sites log file. Default value: <code>false</code>

batch.ini: Results TabProperties in batch.ini: **Results Tab**

Property	Description
request.folder	Specifies the location of the file that stores information about the results of batch processes. For example, the WebCenter Sites publishing system uses this directory to hold the publishing log files. Default value: <code>/dispatcher/</code>

batch.ini: Security TabProperties in batch.ini: **Security Tab**

Property	Description
security.class	Specifies the name of the class file that is used for security checks. The default is provided for reference only: <code>com.openmarket.Batch.DefaultSecurity</code> Do not change the value of this property.

batch.ini: User Defined TabProperties in batch.ini: **User Defined Tab**

Property	Description
----------	-------------

Note: This tab, by default, holds no properties.

catalog.ini

The `catalog.ini` file holds properties that WebCenter Sites uses to configure the shopping cart.

Properties in `catalog.ini` are organized by function on the following tabs in the Property Editor:

- [Catalog Tab](#)
- [User Defined Tab](#)

catalog.ini: Catalog Tab

Properties in `catalog.ini`: **Catalog Tab**

Property	Description
<code>mwb.cartsetdir</code>	<p>Specifies the directory path (including the terminating slash character) where cartset data files are stored.</p> <p>This value is set by the installation. It points to the <code>/gator/cartset</code> directory in the installation directory.</p> <p>Do not change the value of this property.</p>

catalog.ini: User Defined Tab

Properties in `batch.ini`: **User Defined Tab**

Property	Description
----------	-------------

Note: This tab, by default, holds no properties.

commons-logging.properties

The `commons-logging.properties` file is used to specify the WebCenter Sites logging system via the `org.apache.commons.logging.Log` property. Newly installed WebCenter Sites systems use Apache log4j, which is specified as follows:

```
org.apache.commons.logging.Log=  
    com.fatwire.cs.core.logging.Log4JLogger
```

More information about Apache log4j is available in [“log4j.properties”](#) on page 139.

A large variety of other loggers are available in the public domain. You can also write your own loggers if the features sought are not present in any available loggers. If you choose to use Commons Logging with loggers other than log4j, you can still use the Property Editor to view and change log settings.

If the need arises to switch back to the previous Content Server 7.6 Commons Logging system, you will have to manually set `org.apache.commons.logging.Log` to one of the class names listed below:

- TraditionalLog

```
com.fatwire.cs.core.logging.TraditionalLog
```

This logger writes all log messages to the WebCenter Sites log file for each server. TraditionalLog supports log file rolling, custom formatting, date-stamping, and a variety of other features. Optionally, TraditionalLog supports browser-based log retrieval by filtering log messages based on the client’s IP address.

- StandardLog

```
com.fatwire.cs.core.logging.StandardLog
```

This logger also supports custom formatting, date-stamping, and so on, but it sends messages to the standard output and standard error streams; in other words, it sends messages to the java console instead of the WebCenter Sites log file. While StandardLog does not support browser-based log retrieval, it offers another useful feature: It allows developers running a JumpStart Kit or running WebCenter Sites in an IDE debugger to see all of the log messages in the most obvious place. Using StandardLog is good practice for all template developers, because it alerts you to errors by default, as opposed to sending an error to the WebCenter Sites log file, where it requires some effort to be viewed. StandardLog is similar to Apache’s default SimpleLog.

- StandardTraditionalLog

```
com.fatwire.cs.core.logging.StandardTraditionalLog
```

This logger supports the features and output methods of TraditionalLog and StandardLog.

The `commons-logging.properties` file lists the logging properties that can be modified for WebCenter Sites. The properties are organized by function on the following tabs in the Property Editor:

- [Factory Tab](#)
- [Loggers Tab](#)
- [Traditional Log Tab](#)
- [User Defined Tab](#)

commons-logging.properties: AsyncLog Tab

Properties on this tab are deprecated.

Properties in commons-logging.properties: **AsyncLog Tab**

Property	Description
logging.interval	Deprecated. Specifies the time interval (in milliseconds) between writes to the log file. Default value: 5000

commons-logging.properties: Factory TabProperties in commons-logging.properties: **Factory Tab**

Property	Description
org.apache.commons.logging.Log	Specifies the class name implementing the org.apache.commons.logging.Log interface that the default commons-logging log factory will use as the logger. Default value: com.fatwire.cs.core.loggingTraditionalLog The default value names a WebCenter Sites enhanced logger that supports additional features not necessarily supported by other loggers, including browser-based retrieval of the log file, rolling logs, and timestamps. Note: Before modifying the value, consult the commons-logging documentation.
org.apache.commons.logging.LogFactory	Enables a special publishing logger that prints the pubsessionid in each log message when a publishing event is in progress. Use this logger to analyze publishing failures. This property must be manually added to commons-logging.properties. Legal value: com.fatwire.cs.core.logging.ContextAwareLogFactory Note: Enabling this logger automatically disables per-client logging (the value of the logging.per-client-log property is ignored).

commons-logging.properties: Loggers TabProperties in commons-logging.properties: **Loggers Tab**

Property	Description
com.fatwire.logging.cs	<p>Specifies the log severity for the generic WebCenter Sites logger. Messages written to this logger relate to the core WebCenter Sites functionality, or they have not been assigned a more appropriate logger.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.auth	<p>Specifies the log severity for user authentication and user authorization messages. Messages written to this logger relate to user login, user ACLs and user roles.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.blobserver	<p>Specifies the log severity for BlobServer debug messages. Messages written to this logger relate to the addition, retrieval, and modification of data in WebCenter Sites page caches.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.cache.page	<p>Specifies the log severity for page cache debug messages. Messages written to this logger relate to the addition, retrieval, and modification of data in WebCenter Sites page caches.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.cache.resultset	<p>Specifies the log severity for resultset cache debug messages. Messages written to this logger relate to the addition, retrieval, and modification of data in WebCenter Sites resultset caches.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>

Properties in commons-logging.properties: **Loggers Tab** (continued)

Property	Description
com.fatwire.logging.cs.core.http.HttpAccess	<p>Logger used by the HttpAccess API to record errors and warnings encountered during HTTP access. This log produces HTTP Request and Response information, including headers, parameters, and body content. DEBUG generally produces large amounts of log messages.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.core.uri.assembler	<p>Logger used by the URI assembler engine and all assemblers.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.core.uri.definition	<p>Logger used by URI definitions and related implementations.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.db	<p>Specifies the log severity for database access messages. Messages written to this logger relate to database access, queries and statement execution. It can be very helpful to use this logger to debug database queries that are not behaving as expected.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.errno	<p>Logger used to display information related to setting an error number. Messages written by this logger relate to the values set for the Variables.errno and Variables.errdetail WebCenter Sites variables. For more information about setting error numbers, see the <i>WebCenter Sites Developer's Guide</i> and the <i>WebCenter Sites Tag Reference</i>.</p> <p>Possible Values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default Value: INFO</p>

Properties in commons-logging.properties: **Loggers Tab** (continued)

Property	Description
com.fatwire.logging.cs.event	<p>Specifies the log severity for WebCenter Sites event engine messages. Messages written to this logger relate to the invocation of events by WebCenter Sites.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.export	<p>Specifies the log severity for WebCenter Sites page export engine messages. Messages written to this logger relate to the invocation of events by WebCenter Sites.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.filelock	<p>Specifies the log severity for file locking messages.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.firstsite.filter	<p>Logger for FirstSite II filters.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.install	<p>Specifies the log severity for the WebCenter Sites installer's messages. Messages are only written to this log during installation.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.jsp	<p>Specifies the log severity for WebCenter Sites jsp element debug information. Messages written to this logger relate to the invocation of JSP elements by WebCenter Sites.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>

Properties in commons-logging.properties: **Loggers Tab** (continued)

Property	Description
com.fatwire.logging.cs.realtime	<p>Logs operations that take place during the RealTime publishing process.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.request	<p>Specifies the log severity for request processing messages.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.satellite	<p>Generic logger for Satellite Server. Messages logged with this logger pertain to system configuration.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.satellite.cache	<p>This logger for Satellite Server deals with information relating to the parsing of objects that can be cached, as well as their life cycle in the cache.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.satellite.host	<p>This logger for Satellite Server is dedicated to logging information that relates to communication between Satellite Server and its host WebCenter Sites.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.satellite.request	<p>This logger for Satellite Server is dedicated to logging information that relates to processing requests from the client.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>

Properties in commons-logging.properties: **Loggers Tab** (continued)

Property	Description
com.fatwire.logging.cs.session	<p>Specifies the log severity for the WebCenter Sites session logger. Messages written to this logger relate to session creation, modification, and access.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.sync	<p>Specifies the log severity for WebCenter Sites cluster synchronization messages. Messages written to this logger relate to cluster sync behavior of WebCenter Sites.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.sysinfo	<p>Specifies the log severity for capturing system information on the WebCenter Sites installation. This logger is used by the System Tools utility, which is available on the Admin tab, in the WebCenter Sites administrator's interface. For more information about System Tools, see the <i>WebCenter Sites Administrator's Guide</i>.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>

Properties in commons-logging.properties: **Loggers Tab** (continued)

Property	Description
com.fatwire.logging.cs.time	<p>Specifies the log severity for WebCenter Sites time and performance debug information. Messages written to this logger include information that can be used to tune the performance of pages and of WebCenter Sites in general.</p> <p>To log the execution time for pages and pagelets, set this property to <code>DEBUG</code>. When the pages and pagelets are executed, a message similar to the following will be returned:</p> <pre>“Execute page OpenMarket/ Xcelerate/Util/getCurrentUser Hours: 0 Minutes: 0 Seconds: 0:002”</pre> <p>Note: Pages are executed only if they are not found in cache.</p> <p>Possible values: <code>TRACE</code>, <code>DEBUG</code>, <code>INFO</code>, <code>WARN</code>, <code>ERROR</code>, <code>FATAL</code></p> <p>Default value: <code>INFO</code></p>
com.fatwire.logging.cs.visitor.object	<p>Logger for tracking the visitor object life cycle.</p> <p>Possible values: <code>TRACE</code>, <code>DEBUG</code>, <code>INFO</code>, <code>WARN</code>, <code>ERROR</code>, <code>FATAL</code></p> <p>Default value: <code>INFO</code></p>
com.fatwire.logging.cs.visitor.ruleset	<p>Logger for rule set compilation.</p> <p>Possible values: <code>TRACE</code>, <code>DEBUG</code>, <code>INFO</code>, <code>WARN</code>, <code>ERROR</code>, <code>FATAL</code></p> <p>Default value: <code>INFO</code></p>
com.fatwire.logging.cs.xcelerate	<p>Logger for Xcelerate.</p> <p>Possible values: <code>TRACE</code>, <code>DEBUG</code>, <code>INFO</code>, <code>WARN</code>, <code>ERROR</code>, <code>FATAL</code></p> <p>Default value: <code>INFO</code></p>
com.fatwire.logging.cs.xcelerate.advantage.recommendation	<p>Logger for recommendation processing.</p> <p>Possible values: <code>TRACE</code>, <code>DEBUG</code>, <code>INFO</code>, <code>WARN</code>, <code>ERROR</code>, <code>FATAL</code></p> <p>Default value: <code>INFO</code></p>

Properties in commons-logging.properties: **Loggers Tab** (continued)

Property	Description
com.fatwire.logging.cs.xcelerate.approval	<p>Logger for asset approval processing.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.xcelerate.asset	<p>Logger for generic asset processing.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.xcelerate.assetmaker	<p>Logger for assetmaker processing.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.xcelerate.publish	<p>This logger captures publishing logs.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p> <p>Note: DEBUG and TRACE settings produce a large quantity of logs and can severely impact performance.</p>
com.fatwire.logging.cs.xcelerate.template	<p>Logger for Template, CSElement, and SiteEntry asset processing.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
com.fatwire.logging.cs.xml	<p>Specifies the log severity for WebCenter Sites XML element debug information. Messages written to this logger relate to the parsing and evaluation of XML elements. It should be noted that enabling this debug flag will cause WebCenter Sites to use a validating XML parser instead of the default non-validating parser. This can have effects on rendered pages. Consult the documentation for details.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>

Properties in commons-logging.properties: **Loggers Tab** (continued)

Property	Description
com.fatwire.search.asset	<p>Logger used by asset-related search.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
org.apache.http	<p>Top-level logger used by HttpComponents library. For more information, see Apache HttpComponents documentation.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
org.apache.http.client	<p>This logger is used by the HttpComponents library for context logging. For more information, see Apache HttpComponents documentation.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
org.apache.http.impl.client	<p>This logger is used by the HttpComponents library for context logging. For more information, see the Apache HttpComponents documentation.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
org.apache.http.impl.conn	<p>This logger is used by the HttpComponents library for connection management. For more information, see the Apache HttpComponents documentation.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>

Properties in commons-logging.properties: **Loggers Tab** *(continued)*

Property	Description
org.apache.http.headers	<p>This logger is used to log only the http headers. For more information, see the Apache HttpComponents documentation.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: INFO</p>
org.apache.http.wire	<p>This logger is used to log all data transmitted to and from servers when executing HTTP requests. This logger should be enabled only for debugging, as it will produce an extremely large amount of log data, some of it in binary format. For more information, see the Apache HttpComponents documentation.</p> <p>Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL</p> <p>Default value: ERROR</p>

commons-logging.properties: Traditional Log Tab

The table below lists properties that are specific to TraditionalLog, the default logger specified in the property `org.apache.commons.logging.Log`. TraditionalLog supports numerous features that other loggers might not support. In your Spark installation, you may choose to use a different logger with your own set of properties.

Properties in commons-logging.properties: Traditional Log Tab

Property	Description
<code>logging.file</code>	Specifies the full path to the log file. It is required and should be set to a different value for each VM to avoid conflicts. Note: This value must be specified or logging will fail.
<code>logging.format</code>	Specifies the <code>java.text.SimpleDateFormat</code> that will be used in timestamps that are written to the log file. Consult the API documentation for <code>java.text.SimpleDateFormat</code> for syntax information. If not specified, the default <code>SimpleDateFormat</code> will be used.
<code>logging.maxlogsize</code>	Specifies the maximum size of the log file in bytes. Once the log file grows to the size specified, it will either be rolled or deleted. Set it to <code>-1</code> to allow the log to grow indefinitely. Default value: 10MB
<code>logging.per-client-log</code>	Specifies whether a log file will be kept for each distinct IP address that requests data from WebCenter Sites. This property allows the use of CatalogManager to retrieve the log file from a web browser. When this property is set to <code>true</code> , WebCenter Sites creates a log file for each browser IP address. Each file is stored in the same directory as the WebCenter Sites log file and is created according to the following naming convention: <code>futuretense.IPaddress.txt</code> . You can then use the <code>exportlog</code> argument of the CATALOGMANAGER tag to retrieve the log file for the IP address of the browser that you are using. Possible values: <code>true</code> <code>false</code> Note: Per-client logging is automatically disabled if the ContextAwareLogFactory publishing logger is enabled (i.e., the value of <code>logging.per-client-log</code> is ignored when org.apache.commons.logging.LogFactory is set to enable the ContextAwareLogFactory).

Properties in commons-logging.properties: **Traditional Log Tab** *(continued)*

Property	Description
logging.roll	Specifies how many logs will be kept when rolling the log file. Previous versions will be renamed and once all available versions are used, the oldest log will be deleted. Set to 0 to disable rolling of the log file. Set it to a positive integer to specify the number of logs to keep. Default value: 0
logging.timestamp	Specifies whether or not the timestamp will be written to the log file for each logging entry. Possible values: true false Default value: true

commons-logging.properties: User Defined Tab

By default, this tab contains the following properties:

Properties in commons-logging.properties: **User Defined Tab**

Property	Description
com.fatwire.logging.ui.model	This logger is used by the user interface model components. Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL Default value: INFO
com.fatwire.logging.ui.phase	This logger is used by DebugPhaseListener to display the phase of the JSF life cycle. Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL Default value: INFO
com.fatwire.logging.ui.view	This logger is used by the user interface view components. The intended use of this logger is in debugging user interface components and their life cycle. Possible values: TRACE, DEBUG, INFO, WARN, ERROR and FATAL Default value: INFO

Properties in commons-logging.properties: **User Defined Tab** *(continued)*

Property	Description
com.fatwire.search. lucene	This logger is used by the Lucene integration. Possible values: TRACE, DEBUG, INFO, WARN, ERROR, FATAL Default value: INFO

CSPortletRequest.properties

The `CSPortletRequest.properties` file holds portal configuration properties that are set by the WebCenter Sites installation program.

The following tab is displayed (in the Property Editor) for the `CSPortletRequest.properties` file:

- [User Defined Tab](#)

Caution

Do **not** change the values of any properties on this tab.

CSPortletRequest.properties: User Defined Tab

Properties in `CSPortletRequest.properties`: **User Defined Tab**

Property	Value
<code>cs.contenttype.UTF-8</code>	<code>text/html; charset=UTF-8</code>
<code>cs.charset</code>	<code>_charset_</code>
<code>cs.contenttype</code>	<code>text/html; charset=UTF-8</code>
<code>cs.disksize</code>	<code>102400</code>

dir.ini

The `dir.ini` file contains properties that are used to configure the directory services options described below.

The `dir.ini` file is the main configuration file for WebCenter Sites' Directory Services API. WebCenter Sites uses this API to connect to directory servers for authentication/authorization services and to provide the following options for managing user information (one of the options is configured for your WebCenter Sites system):

- The WebCenter Sites directory services plug-in, which uses the native WebCenter Sites user management tables (`SystemUsers` and `SystemUserAttrs`).
- LDAP plug-ins, which uses the directory server rather than the WebCenter Sites database to store user names and attributes.

Properties in `dir.ini` are organized by function on the following tabs in the Property Editor:

- [Attribute Names Tab](#)
- [Compatibility Tab](#)
- [Global Data Tab](#)
- [Interface Implementations Tab](#)
- [JNDI SPI Env. Tab](#)
- [Naming Syntax Tab](#)
- [Schema Defaults Tab](#)
- [Search Controls Tab](#)
- [User Defined Tab](#)

Note

Although the `dir.ini` file is the main configuration file for the directory services API, there are additional user manager/directory services properties in another property file, `futuretense.ini`. See "[Authentication Tab](#)" on page 52.

dir.ini: Attribute Names Tab

The **Attribute Names** tab holds attribute-mapping properties. You use these properties to specify how a user attribute used by WebCenter Sites is identified in the directory server.

Properties in `dir.ini`: **Attribute Names** Tab

Property	Description
<code>cn</code>	<p>Specifies the name of the attribute in the directory server that serves as the group name attribute.</p> <p>Possible values:</p> <ul style="list-style-type: none">• WebCenter Sites and NT: <code>cn</code>• LDAP, iPlanet: <code>cn</code>• LDAP, Active Directory: <code>cn</code>
<code>loginattribute</code>	<p>Specifies the name of the attribute in the directory server that serves as the user login attribute.</p> <p>Default value: <code>uid</code></p>
<code>password</code>	<p>Specifies the name of the attribute in the directory server that serves as the password attribute.</p> <p>Possible values:</p> <ul style="list-style-type: none">• WebCenter Sites and NT: <code>password</code>• LDAP, iPlanet: <code>userPassword</code>• LDAP, Active Directory: <code>password</code>
<code>uniquemember</code>	<p>Specifies the name of the attribute in the directory server that serves as the group assignment attribute.</p> <p>Possible values:</p> <ul style="list-style-type: none">• WebCenter Sites and NT: <code>uniquemember</code>• LDAP, iPlanet: <code>uniquemember</code>• LDAP, Active Directory: <code>member</code>

Properties in `dir.ini`: **Attribute Names Tab** (*continued*)

Property	Description
username	<p>Specifies the name of the attribute in the directory server that serves as the user name attribute.</p> <p>Possible values:</p> <ul style="list-style-type: none">• WebCenter Sites and NT: username• LDAP, iPlanet: uid• LDAP, Active Directory: sAMAccount
memberof	<p>Specifies the name of the user attribute that contains information about the user's groups.</p> <p>If a user's membership in a group is specified by the <code>uniquemember</code> attribute on the group, leave this property blank.</p> <p>If the group membership of a user is specified by an attribute of the user, specify the name of that attribute here.</p> <p>Possible values:</p> <ul style="list-style-type: none">• LDAP, WebLogic embedded LDAP: wlsmemberof• LDAP, SunONE Identity Server: memberof

dir.ini: Compatibility Tab

The **Compatibility** tab holds properties that determine how any strings that are extracted from the directory server and stored in the WebCenter Sites database are treated.

Properties in `dir.ini`: **Compatibility** Tab

Property	Description
<code>cleandns</code>	<p>Specifies how the strings for distinguished names are stored in the WebCenter Sites database.</p> <p>If set to true, the Directory Services API extracts distinguished names from the directory server, and then removes extra spaces from them and then changes all the upper-case letters to lower-case letters before storing the strings in the WebCenter Sites database.</p> <p>Possible values: <code>true</code> <code>false</code></p> <p>Default value: <code>false</code></p> <p>Note: Do not set this value to <code>true</code> if you are upgrading from an earlier version of WebCenter Sites. If you do, you must manually change any existing dns strings that are stored in the WebCenter Sites tables. Also, if you set it to <code>true</code>, you must also verify that the <code>syntax.ignorecase</code> property is also set to <code>true</code>.</p>

dir.ini: Global Data Tab

The **Global Data** tab holds properties that determine global values for all users.

Properties in `dir.ini`: **Global Data** Tab

Property	Description
<code>baseDN</code>	<p>Specifies the distinguished name for the root to use by default for searches and for prepending to the names for attribute values that require a DN type.</p> <p>Default value: blank</p> <p>Do not change the value of this property. Because the authentication module sets the <code>currentUser</code> session variable to a fully qualified name, WebCenter Sites assumes that all names returned from the search are fully qualified.</p>
<code>groupparent</code>	<p>Specifies the entry to use as the parent of all WebCenter Sites entries of type <code>Group</code>.</p> <p>Possible values:</p> <ul style="list-style-type: none"> WebCenter Sites and NT: ou=groups LDAP, iPlanet: ou=groups,dc=<companyname>,dc=com LDAP, Active Directory: cn=groups,dc=<companyname>,dc=com
<code>peopleparent</code>	<p>Specifies the entry to use as the parent of all WebCenter Sites entries of type <code>User</code>.</p> <p>Possible values:</p> <ul style="list-style-type: none"> WebCenter Sites and NT: ou=people LDAP, iPlanet: cn=people,dc=<companyname>,dc=com LDAP, Active Directory: cn=users,dc=<companyname>,dc=com

dir.ini: Interface Implementations Tab

The **Interface Implementations** tab holds two properties that determine which user manager module your WebCenter Sites system is using. The properties are `className.IDir` and `className.IName`. The values of the properties on the **Interface Implementations** tab should not be modified unless you are integrating with LDAP.

Properties in `dir.ini`: **Interface Implementations** Tab

Property	Description
<code>className.Attribute</code>	Specifies the name of the concrete class to implement the interface <code>Attribute</code> . Do not change the value of this property unless you are integrating with LDAP.
<code>className.Attributes</code>	Specifies the name of the concrete class to implement the interface <code>Attributes</code> . Do not change the value of this property unless you integrate with LDAP.
<code>className.IDir</code>	With the <code>className.IName</code> property, specifies which user manager module your system is using. Possible values: <ul style="list-style-type: none"> WebCenter Sites: <code>com.openmarket.directory.cs.CSDir</code> LDAP: <code>com.openmarket.directory.jndi.JNDIDir</code> Do not change the value of this property unless you are integrating with LDAP.
<code>className.IFactory</code>	Specifies the name of the concrete class to implement the interface <code>IFactory</code> . Do not change the value of this property unless you are integrating with LDAP.
<code>className.IName</code>	With the <code>className.IDir</code> property, specifies which user manager module your system is using. Possible values: <ul style="list-style-type: none"> WebCenter Sites: <code>com.openmarket.directory.cs.CSName</code> LDAP: <code>com.openmarket.directory.jndi.NameWrapper</code> Do not change the value of this property unless you are integrating with LDAP.

Properties in `dir.ini`: **Interface Implementations Tab** (*continued*)

Property	Description
<code>className.IUserDir</code>	<p>Specifies the name of the concrete class to implement interface <code>IUserDir</code>.</p> <p>Possible values:</p> <ul style="list-style-type: none">• WebCenter Sites: <code>com.openmarket.directory.cs.CSDir</code>• LDAP: <code>com.openmarket.directory.jndi.LDAPUserDir</code> <p>Do not change the value of this property unless you are integrating with LDAP.</p>
<code>className.JNDIName</code>	<p>Specifies the name of the concrete class to implement the interface <code>JNDIName</code>.</p> <p>Do not change the value of this property unless you are integrating with LDAP.</p>

dir.ini: JNDI SPI Env. Tab

The properties on the **JNDI SPI Env** tab are used only if your WebCenter Sites system is configured to use the LDAP user manager module.

Properties in `dir.ini`: **JNDI SPI Env** Tab

Property	Description
<code>java.naming.factory.initial</code>	<p>Specifies the initial factory class to use. The value of this property should be the fully qualified class name of the factory class that will create an initial context.</p> <p>Do not change the value of this property.</p>
<code>java.naming.security.authentication</code>	<p>Specifies the security level to use. Its value is one of the following strings: <code>none</code>, <code>simple</code>, <code>strong</code>.</p> <p>If this property is unspecified, the security level is determined by the service provider.</p> <p>Default value: <code>simple</code></p>
<code>jndi.baseURL</code>	<p>Specifies the server name and port number of the directory server.</p> <p>The value uses the following format:</p> <p><code>ldap://<hostname>:<port></code></p>
<code>jndi.connectAsUser</code>	<p>Specifies whether WebCenter Sites needs a designated user account to query the directory server for user attribute information.</p> <p>If set to <code>true</code>, <code>jndi.connectAsUser</code> specifies a WebCenter Sites login to the LDAP server. This means that WebCenter Sites queries the directory server for information as the user who is logged in to the WebCenter Sites system and is making the inquiry. For example, when an administrator examines user information in the WebCenter Sites interface, WebCenter Sites makes the inquiry as that user (admin, for example.)</p> <p>If set to <code>false</code>, <code>jndi.connectAsUser</code> specifies a direct login to the LDAP server. This means there must be a valid username/password combination specified for the <code>jndi.login</code> and <code>jndi.password</code> properties; WebCenter Sites uses that user account to make inquiries.</p>
<code>jndi.custom</code>	<p>System property.</p> <p>Do not enter a value for this property.</p> <p>Specifies other spi-specific variables to pass into the <code>javax.naming.context</code>. Syntax follows <code>x-www-form-urlencoded</code> format.</p>

Properties in `dir.ini`: **JNDI SPI Env Tab** (*continued*)

Property	Description
<code>jndi.login</code>	<p>Applies only when <code>jndi.connectAsUser</code> is set to <code>false</code>.</p> <p>Specifies the fully qualified, fully distinguished name of the user account that WebCenter Sites uses to query the directory server.</p>
<code>jndi.password</code>	<p>Applies only when <code>jndi.connectAsUser</code> is set to <code>false</code>.</p> <p>Specifies the password of the user account that WebCenter Sites uses to query the directory server. This value is encrypted.</p>
<code>jndi.poolConnections</code>	<p>Applies only when <code>jndi.connectAsUser</code> is set to <code>false</code>.</p> <p>If this property is set to <code>true</code>, the system will create a pool of <code>DirContent</code> connections.</p> <p>If set to <code>false</code>, <code>jndi.poolsize</code> is ignored.</p>
<code>jndi.poolsize</code>	<p>Indicates the size of the pool.</p> <p>Default value: 20</p> <p>This property is ignored if <code>jndi.poolConnections</code> is set to <code>false</code>.</p>
<code>syntax.custom</code>	<p>Specifies <code>classJNDIName</code>-specific variables to pass into the <code>classIName</code> constructor. Syntax follows <code>x-www-form-urlencoded</code> format.</p>

dir.ini: Naming Syntax Tab

The **Naming Syntax** tab holds properties that determine how strings for user attributes and their values are interpreted.

Properties in `dir.ini`: **Naming Syntax Tab**

Property	Description
<code>syntax.beginquote</code>	Specifies the string that delimits the beginning of a quoted string. Default value: <code>'</code>
<code>syntax.beginquote2</code>	Specifies an alternative to the value specified for the <code>syntax.beginquote</code> property.
<code>syntax.direction</code>	Specifies the direction in which the components in a designated name are read. Possible values: <code>left_to_right</code> <code>right_to_left</code> <code>flat</code> Default value: <code>left_to_right</code>
<code>syntax.endquote</code>	Specifies the string that delimits the end of a quoted string. Default value: <code>'</code>
<code>syntax.endquote2</code>	Specifies an alternative to the value specified for <code>syntax.endquote</code> .
<code>syntax.escape</code>	Specifies the escape string for overriding separators, escapes, and quotes. If you are using special characters, such as <code>'</code> , <code>,</code> , <code>+</code> , <code>-</code> , <code>;</code> , etc., in DN, you cannot use <code>\</code> as an escape string. Default value: <code>\</code>

Properties in dir.ini: **Naming Syntax** Tab *(continued)*

Property	Description
<code>syntax.ignorecase</code>	<p>Specifies whether strings are case-sensitive or not.</p> <p>Set to <code>false</code> if the uppercase and the lowercase version of a letter character should be considered as different characters. (That is, “admin” and “Admin” should be interpreted as different words.)</p> <p>Set to <code>true</code> if you want the uppercase and the lowercase version of a letter character to be considered as the same character. (That is “admin” and “Admin” should be interpreted as the same string.)</p> <p>Default value: <code>true</code></p> <p>Note: If you need to set the <code>cleandns</code> property on the Compatibility tab to <code>true</code>, you must also set this property’s value to <code>true</code>.</p>
<code>syntax.separator</code>	<p>Specifies the separator character used between atomic name components.</p> <p>This property is required unless <code>syntax.direction</code> is set to a value of <code>flat</code>.</p> <p>Default value: <code>,</code></p>
<code>syntax.separatorava</code>	<p>Specifies the separator character used to separate multiple attribute/value pairs. Typically the comma character (,) is used.</p> <p>Default value: <code>,</code></p>
<code>syntax.separatortypeval</code>	<p>Specifies the separator character used to separate an attribute from its value. For example, the equals symbol (=) is used.</p> <p>Default value: <code>=</code></p>
<code>syntax.trimblanks</code>	<p>Specifies whether spaces and whitespace characters are significant or should be ignored (trimmed) when evaluating a string.</p> <p>Set to <code>true</code> if spaces should be ignored.</p> <p>Set to <code>false</code> if spaces should be considered when evaluating a string.</p> <p>Default value: <code>false</code></p>

dir.ini: Schema Defaults Tab

The **Schema Defaults** tab holds properties that identify the following entities to WebCenter Sites:

- The directory server attributes for which users must have values in order to be valid users
- Attribute values that are assigned to users by default (if any).

Properties in `dir.ini`: **Schema Defaults Tab**

Property	Description
<code>defaultGroupAttrs</code>	<p>Specifies the attribute name/value pairs that are set for every descendent of the entry specified by the <code>groupparent</code> property.</p> <p>WebCenter Sites uses this information to create the default groups that it needs during the installation, which means that this property must be set before you install WebCenter Sites.</p> <p>Values must be entered in the x-www-form-urlencoded format.</p>
<code>defaultPeopleAttrs</code>	<p>Specifies the attribute name/value pairs that are set for every descendent of the entry specified by the <code>peopleparent</code> property.</p> <p>WebCenter Sites uses this information to create the default users that it needs during the installation, which means that this property must be set before you install WebCenter Sites.</p> <p>Values must be entered in the x-www-form-urlencoded format.</p>
<code>defaultReaderACLs</code>	<p>The ACL list to be assigned to DefaultReader by Login Module.</p> <p>Default value: <code>Browser</code></p>
<code>objectclassGroup</code>	<p>Specifies the name of the base object that signifies a WebCenter Sites group. The <code>DIR.GROUPMEMBERSHIPS</code> tag uses the value set for this property to differentiate group entries from user or other entries.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • WebCenter Sites: <code>groupofuniquenames</code> • LDAP, iPlanet: <code>groupofuniquenames</code> • LDAP, Active Directory: <code>group</code>

Properties in `dir.ini`: **Schema Defaults** Tab *(continued)*

Property	Description
<code>objectclassPerson</code>	<p>Specifies the name of the base object that signifies a WebCenter Sites user (person). The <code>DIR.LISTUSERS</code> tag uses the value set for this property to differentiate user entries from group or other entries</p> <p>Value for WebCenter Sites or LDAP: <code>person</code></p>
<code>requiredGroupAttrs</code>	<p>Specifies the attributes that every descendent of the entry specified by the <code>groupParent</code> property must have values for.</p> <p>Values must be entered in the x-www-form-urlencoded format.</p>
<code>requiredPeopleAttrs</code>	<p>Specifies the attributes that every descendent of the entry specified by the <code>peopleParent</code> property must have values for.</p> <p>Values must be entered in the x-www-form-urlencoded format.</p>

dir.ini: Search Controls Tab

The **Search Controls** tab holds properties that constrain the queries that the user manager plug-in makes to the directory server.

Properties in `dir.ini`: **Search Controls Tab**

Property	Description
<code>search.returnLimit</code>	Specifies the maximum number of entries to return. To obtain all the entries that satisfy the search criteria, set the value to 0.
<code>search.scope</code>	Specifies to what depth in the hierarchy a search reaches: search just the specified or current node, or search the nodes under that node. Default value: 2 (which means search all nodes under the stated node)
<code>search.timeoutVal</code>	Specifies the number of seconds to wait for results before returning an error. A value of 0 means to wait indefinitely (that is, wait until the network timeout limit ends the wait).

dir.ini: User Defined TabProperties in `dir.ini`: **User Defined Tab**

Property	Description
----------	-------------

Note: This tab, by default, has no properties.

fatwire_settings.properties

The `fatwire_settings.properties` file holds the property that points to the e-mail address which will receive “forgotten password” notices from WebCenter Sites users.

fatwire_settings.properties: User Defined Tab

Properties: `fatwire_settings.properties`: **User Defined Tab**

Property	Description
<code>forgotpassword</code>	<p>Specifies the e-mail address that should receive notices from users regarding forgotten passwords. This property sets the e-mail address for the Forgotten Password? link on the WebCenter Sites login page.</p> <p>Legal value: <e-mail address></p> <p>Default value: <code>admin@localhost</code></p>

futuretense.ini

The `futuretense.ini` file is the main property file for WebCenter Sites. Its properties are organized by function on the following tabs in the Property Editor:

- [App Server Tab](#)
- [Authentication Tab](#)
- [Basic Tab](#)
- [Blob Server Tab](#)
- [Cluster Tab](#)
- [Compatibility Tab](#)
- [Content Tables Tab](#)
- [Database Tab](#)
- [Debug Tab](#)
- [Email Tab](#)
- [Export/Mirror Tab](#)
- [JSP Tab](#)
- [Misc Tab](#)
- [Page Cache Tab](#)
- [ResultSet Cache Tab](#)
- [Satellite Server Tab](#)
- [Search Tab](#)
- [User Defined Tab](#)

futuretense.ini: App Server Tab

The **App Server** tab holds the `futuretense.ini` properties that supply information to WebCenter Sites about the application server.

Properties in `futuretense.ini`: App Server Tab

Property	Description
<code>cs.eventhost</code>	<p>The host string for running the event engine on application servers. In a clustered environment, this property must be set on each cluster member and point to either the primary cluster member or to the cluster member, itself. The second option provides for failover.</p> <p>Legal value: <code>http://<hostname>:<port_number></code></p>
<code>ft.cgipath</code>	<p>The web server CGI directory where WebCenter Sites objects are installed.</p> <p>Used in the constructions of URLs and form actions.</p> <p>Be sure the value ends with a forward slash (/).</p> <p>Possible values:</p> <p><code>/NASApp/CS/</code> – when using the Sun ONE application server (iAS); the path is defined to be the path used when installing Sun ONE.</p> <p><code>/servlet/</code> – in http servlet application environments (such as WebLogic).</p>

futuretense.ini: Authentication Tab

The **Authentication** tab holds user authentication properties that are configured during installation based on the user manager plug-in in use on your WebCenter Sites system. Some of these properties apply no matter which user management module you are using, while others apply only if you are using NT authentication.

See also, the main configuration file for the user manager plug-ins is the `dir.ini` file. See [“dir.ini”](#) on page 35.

Properties in futuretense.ini: Authentication Tab

Property	Description
<code>cs.manageACL</code>	Specifies the class that replaces the default WebCenter Sites ACL name-to-privilege mask function. Do not change the value of this property.
<code>cs.manageproperty</code>	Specifies the name of the appropriate property file that configures the LDAP plug-in or the NT authentication plug-in, depending on whether you are using either of these user manager modules. <ul style="list-style-type: none"> • For LDAP, set the value to: <code>dir.ini</code> • For NT, set the value to: <code>futuretense.ini</code>
<code>cs.manageUser</code>	Specifies which user manager plug-in to use with this WebCenter Sites system. <ul style="list-style-type: none"> • If you are using the default WebCenter Sites plug-in, the value is blank. WebCenter Sites will use database authentication and authorization. • If you are using LDAP, the value is: <code>com.openmarket.directory.jndi.auth.JNDILogin</code> • If you are using NT authentication, the value is: <code>com.FutureTense.NTUserGroups.ValidateLogin.NTUserGroupsLogin</code> <p>This property is set when your WebCenter Sites system is integrated with LDAP or a different external system. Do not change its value after installation. By default, the value is blank.</p> <p>Note: When this property is set, the <code>cs.manageproperty</code> must also be set.</p>
<code>cs.manageUserAccess</code>	Specifies the class that replaces the default WebCenter Sites user-to-privilege-by-resource lookup functionality. Do not change the value of this property.

Properties in futuretense.ini: **Authentication Tab** (continued)

Property	Description
<code>cs.manageUserSystem</code>	<p>Applies only when your WebCenter Sites system is using NT authentication (that is, <code>cs.manageUser</code> points to the NT plug-in).</p> <p>Specifies a comma-separated list of NT domain names that WebCenter Sites uses to authenticate users.</p> <p>Authentication is done in the order specified by the list of domains. A user is declared a valid user if his username/password combination is found in any of those domains.</p> <p>Specify the local system with a period (.) character.</p> <p>If the <code>cs.manageUser</code> points to the NT plug-in, but there are no domain names set for this property, WebCenter Sites attempts authentication on the local NT domain only.</p> <p>This value was set during installation.</p>
<code>cs.ssovalidator</code>	<p>This property points to the SSO validator plug-in.</p> <p>Given that the WEM Framework is installed by default, the default value is:</p> <pre>com.fatwire.wem.sso.cas.cs.plugin. SSOValidatorPlugin</pre>
<code>ntlogin.DefaultACL</code>	<p>NT user manager plug-in only.</p> <p>A comma-separated list of any ACLs that should be assigned to all users by default.</p> <p>By default, this value is blank.</p>
<code>ntlogin.DefaultReaderACL</code>	<p>NT user manager plug-in only.</p> <p>The ACL list to be assigned to the account that is used as the default reader account.</p> <p>By default, this value is blank.</p>
<code>ntlogin.DefaultReaderID</code>	<p>NT user manager plug-in only.</p> <p>The user name to be used as the default reader account.</p> <p>By default, it is set to <code>DefaultReader</code>.</p> <p>This value can be blank.</p>

Properties in futuretense.ini: **Authentication Tab** (continued)

Property	Description
ntlogin.DefaultReaderPW	<p>NT user manager plug-in only.</p> <p>The password for the user name that the NT authentication module uses as the default reader account. Required if there is a value for ntlogin.DefaultReaderID.</p> <p>By default, it is set to SomeReader. The value is encrypted.</p>
ntlogin.LogFile	<p>NT user manager plug-in only.</p> <p>The complete path to the file where debug information from the NT authentication module should be written. (Used only when ntlogin.Logging is set to true.)</p>
ntlogin.Logging	<p>NT user manager plug-in only.</p> <p>Enables or disables debugging for the NT authentication module.</p> <p>Possible values: true false</p>
singlesignon	<p>If set to true, enables single sign-on for an authentication plug-in that supports single sign-on.</p> <p>Because the WEM Framework is installed by default, this property is set to true.</p>

futuretense.ini: Basic Tab

The **Basic** tab holds the `futuretense.ini` properties that control such things as security settings, session timeouts, and Global Unique Identifiers that the WebCenter Sites servlets use.

Properties in `futuretense.ini`: **Basic Tab**

Property	Description
<code>bs.security</code>	<p>Specifies whether the BlobServer servlet checks security before allowing database access and image retrieval. If security is on, images cannot be cached in memory.</p> <p>If you enable BlobServer security, the BlobServer servlet serves the data only if the <code>csblobid</code> parameter exists in the URL and its value matches a session variable of the same name, as in the following example:</p> <pre></pre> <p>Possible values: <code>true</code> <code>false</code></p>
<code>cc.security</code>	<p>Specifies whether WebCenter Sites checks security before allowing database access. This property should always be set to <code>true</code> except in special cases.</p> <p>Possible values: <code>true</code> <code>false</code></p>
<code>cs.barEqualsSlash</code>	<p>Specifies whether an Internet Explorer browser should interpret the bar (<code> </code>) character as a forward slash (<code>/</code>) when it is included in a page name.</p> <p>Possible values: <code>true</code> <code>false</code></p> <p>For example, when set to <code>true</code>, Internet Explorer interprets <code>pagename=folder subfolder page</code> as the same page as <code>pagename=folder/subfolder/page</code></p> <p>Default value: <code>false</code></p>
<code>cs.session</code>	<p>Specifies whether WebCenter Sites starts and maintains a browser session for each user.</p> <p>Possible values: <code>true</code> <code>false</code></p> <p>Cannot be set to <code>false</code> when the <code>cc.security</code> property is set to <code>true</code>.</p>

Properties in futuretense.ini: **Basic Tab** (continued)

Property	Description
cs.timeout	<p>Specifies the number of seconds a connection can remain idle before the application server logs out this connection, which ends a browser session. Idle time is the time between WebCenter Sites http requests.</p> <p>Default value: 300 (5 minutes)</p> <p>Note: When the approval system approves assets, it is not a background process. Therefore, if you use the Approve Multiple Assets feature, be sure to set this property to a value that is greater than the amount of time it takes to approve a batch of asset so that the browser session does not time out. You will have to experiment with this setting, but you can start by setting it to 1800 seconds (30 minutes).</p>
cs.uniqueidpoolsize	<p>Specifies the number of unique and cluster-safe ID numbers that are cached at one time. (WebCenter Sites generates unique IDs for every row in any database table.)</p> <p>Default value: 100</p>
cs.wrapper	<p>Deprecated. Specifies whether the WebCenter Sites HTML wrapper pages should (can) be used.</p> <p>Default value: true</p> <p>Set this value to <code>false</code> on a WebCenter Sites system in which the application server does not have HTTP access to the web server, or, if you have removed the directory that holds the wrapper pages for security reasons.</p> <p>See also the <i>WebCenter Sites Administrator's Guide</i>.</p>
ft.version	<p>Specifies the version number of the WebCenter Sites application.</p> <p>Do not modify this value.</p>
secure.CatalogManager	<p>Specifies whether the DefaultReader user can access the CatalogManager servlet.</p> <p>Possible values: true false</p> <p>During installation, this property is set to <code>false</code>. Be sure that this value is changed to <code>true</code> after the installation.</p> <p>For more information, see the <i>WebCenter Sites Administrator's Guide</i>.</p>

Properties in `futuretense.ini`: **Basic** Tab (continued)

Property	Description
<code>secure.DebugServer</code>	<p>Controls whether <code>DefaultReader</code> can connect to the specified servlet when security is on. If set to <code>true</code>, <code>DefaultReader</code> cannot connect.</p> <p>Possible values: <code>true</code> <code>false</code></p>
<code>secure.TreeManager</code>	<p>Specifies whether the <code>DefaultReader</code> user can access the <code>TreeManager</code> servlet.</p> <p>Default value: <code>true</code></p> <p>For more information, see the <i>WebCenter Sites Administrator's Guide</i>.</p>

futuretense.ini: Blob Server Tab

The **BlobServer** tab holds properties that configure the BlobServer servlet. BlobServer serves blobs. It gathers a blob from a table and performs all the necessary security checks. When BlobServer serves a blob, it caches it in both WebCenter Sites and Satellite Server.

Properties in `futuretense.ini`: **Blob Server Tab**

Property	Description
<code>bs.bCacheSize</code>	<p>Specifies the default number of blobs that can be cached (to memory).</p> <p>Default value: 100</p>
<code>bs.bCacheTimeout</code>	<p>Specifies the number of seconds that a blob will remain cached in memory. Note that the memory cache is cleared whenever the BlobServer servlet is restarted.</p> <p>This property affects the operation of CacheManager as follows:</p> <p>When compositional dependencies are recorded against a blob in the <code>SystemItemCache</code> table, they are configured such that they will be removed from the table after the blob expires from the cache. This prevents excessive growth of the <code>SystemItemCache</code> table. However, removing the entry from the table disables CacheManager from removing the corresponding blobs from the Tier 2 cache, and users will view stale data.</p> <p>Possible values: negative integer, 0, positive integer</p> <p>Default value: -1</p> <p>The blob will remain cached in memory forever, unless it is evicted because more recently used blobs have filled the cache.</p> <p>Note: The value of this property affects <code>cs.manage.expired.blob.inventory</code> as follows:</p> <ul style="list-style-type: none"> • A value of 0 or less causes <code>cs.manage.expired.blob.inventory</code> to have no effect. • A positive integer with <code>cs.manage.expired.blob.inventory</code> set to true ensures that CacheManager operates correctly, but at the cost of growth in the <code>SystemItemCachetable</code>. <p>For more information about cs.manage.expired.blob.inventory, see page 83.</p>

Properties in futuretense.ini: **Blob Server Tab** *(continued)*

Property	Description
<code>bs.invalidheadernames</code>	<p>Comma separated list of invalid headers which are ignored by BlobServer.</p> <p>Default value: Set-Cookie</p>
<code>cs.recordBlobInventory</code>	<p>Specifies whether compositional dependencies should be recorded against blobs. This property must be set to <code>true</code> (the default) for CacheManager to operate on blobs.</p> <p>Possible values: <code>true false</code></p> <p>Default value: <code>true</code></p>

futuretense.ini: Cluster Tab

The **Cluster** tab holds the properties that WebCenter Sites uses to communicate with all the servers in a cluster when a WebCenter Sites system is installed in a cluster.

Properties in `futuretense.ini`: **Cluster Tab**

Property	Description
<code>cc.cacheNoSync</code>	<p>Specifies whether the system allows the database query transaction data cached by WebCenter Sites to persist even if a cluster member updates the table.</p> <p>Default value: <code>false</code></p> <p>You can set table-specific values for individual tables by adding a property in the following format:</p> <p><code>cc.<sometable>CSync=<true or false></code></p>
<code>ft.sync</code>	<p>An identifier or value that defines the synchronizer key for clustered servers; for example, the DSN that cluster members use for their shared database. Each cluster member must have the same <code>ft.sync</code> value.</p> <p>When set to <code>true</code> or <code>yes</code>, <code>sync</code> is enabled and extra asset-level locking is in effect. This mode is intended for clustered editorial systems, as it uses an asset-locking mechanism designed for frequent changes to assets.</p> <p>When set to a value other than <code>true</code> or <code>yes</code>, <code>sync</code> is enabled but extra asset-level locking is not in effect. This mode is intended for clustered delivery systems, as it enables an asset-locking mechanism designed for infrequent changes to assets.</p> <p>Note: Oracle recommends that you specify a value for <code>ft.sync</code>.</p> <p>Legal values: <code><string></code> <code><blank></code></p>
<code>ft.usedisksync</code>	<p>Specifies a shared file system folder to synchronize data across a cluster.</p> <p>Set this property to a valid folder when synchronization is turned on with the <code>ft.sync</code> property. For example, set it to a directory where you have read/write access.</p>

futuretense.ini: Compatibility Tab

The **Compatibility** tab holds properties that set values necessary for backward compatibility with earlier versions of WebCenter Sites.

Properties in `futuretense.ini`: **Compatibility** Tab

Property	Descriptions
<code>cs.cookievariables</code>	<p>Specifies if cookie variables should be created for servlet request information.</p> <p>Generating cookie variables can confuse page criteria for page requests and works only for outer pages.</p> <p>Legal value: <code>false</code></p>
<code>cs.dataindatabase</code>	<p>Specifies whether large data should be saved in the database or in the file system as an upload column.</p>
<code>cs.httpvariables</code>	<p>Deprecated.</p> <p>Specifies whether the WebCenter Sites variables that contain HTTP header information are created on each page request, as was necessary in pre-4.0 versions of the product. Starting with 4.0, FatWire Content Server provides built-in variables that perform the same function.</p> <p>Default value: <code>false</code></p> <p>For best performance, leave this value set to <code>false</code>. If developers need to retrieve an http variable for a site page, they can retrieve the value of the ones they need by using the built-in variables.</p>
<code>cs.satellitehosts</code>	<p>Specifies the host names of the servers that are hosting Satellite servlets that the CacheManager on this server (the one that hosts WebCenter Sites) needs to communicate with.</p> <p>Enter a comma-separated list of host names. The value for each host must include the path to the WebCenter Sites servlets.</p> <p>Use the following format:</p> <p><code>http://<hostname:port>/<servlet>/</code></p> <p>You can use https or special ports, if necessary. If required by your configuration, be sure to specify a fully-qualified domain name.</p> <p>The Satellite servlet that resides on this server is listed by default.</p>

Properties in `futuretense.ini`: **Compatibility Tab** (continued)

Property	Descriptions
<code>cs.satellitepassword</code>	<p>Specifies the passwords for the user accounts specified by the <code>cs.satelliteusers</code> property. Note that the password for the Satellite servlet on this server is listed by default.</p> <p>The value of this property is encrypted as a single string. Therefore, when you edit the value of this property, you must enter all the passwords for all the Satellite servlet hosts, including the comma delimiter.</p> <p>Enter a comma-separated list of passwords in the order that matches the order in which you enter the corresponding users for the <code>cs.satelliteusers</code> property. Be sure that the order of this list also matches the order of the list of host names provided for the <code>cs.satellitehosts</code> property.</p>
<code>cs.satelliteusers</code>	<p>Specifies the user names for the Satellite Server hosts. Note that the user name for the Satellite servlet on this server is listed by default.</p> <p>Enter a comma-separated list of user names in the order that matches the list of passwords that you specified for the <code>cs.satellitepassword</code> property.</p>
<code>cs.selfmodify</code>	<p>Specifies a comma-separated list of attributes that a user is allowed to modify.</p> <p>Currently, only <code>password</code> is supported.</p> <p>For complete backward compatibility, set the property to blank to ensure that the user has write privileges to the <code>SystemUsers</code> table.</p>
<code>cs.xmlHeaderAutoStream</code>	<p>Tells WebCenter Sites whether it should stream the XML header as defined in the property <code>cs.xmlHeader</code> as the first content of the response, automatically, or not.</p> <p>If this property is set to <code>true</code>, then WebCenter Sites will automatically insert the header into the response. If it is set to <code>false</code>, then WebCenter Sites will not do anything. If the response is not a SOAP response, this property is ignored entirely and the header is never inserted.</p> <p>Default value: <code>false</code></p>
<code>ft.approot</code>	<p>Deprecated.</p> <p>This property is no longer used. In some cases, it may be required for backward compatibility.</p>

Properties in `futuretense.ini`: **Compatibility** Tab (continued)

Property	Descriptions
<code>ft.catalogmanager</code>	<p>Defines the Global Unique Identifier (GUID) for the CatalogManager service. It is provided for reference only.</p> <p>Default value: {40DD4E30-8DE2-11D1-8599-0080C7D07E91}</p> <p>Do not modify this value.</p>
<code>ft.contentserver</code>	<p>Defines the GUID for the ContentServer servlet. It is provided for reference only.</p> <p>Default value: {29434AD0-8DE2-11D1-8599-0080C7D07E91}</p> <p>Do not modify this value.</p>
<code>ft.treemanager</code>	<p>Defines the GUID for the Treemanager servlet.</p> <p>Do not modify this value.</p>
<code>security.checkpagelets</code>	<p>Specifies whether WebCenter Sites checks security before allowing a user to view a pagelet that is nested in an enclosing page.</p> <p>Note that the <code>cc.security</code> property must also be set to <code>true</code> for security to be implemented.</p> <p>Default value: <code>true</code></p> <p>If set to <code>false</code>, the following occurs:</p> <ul style="list-style-type: none"> On systems with co-resident Satellite Server, security is not checked on any pages or pagelets, even with <code>cc.security</code> set to <code>true</code>. On systems with stand-alone Satellite Server or with WebCenter Sites only, security is checked on the first or outermost page but security is not checked on nested pagelets.

futuretense.ini: Content Tables Tab

The **Content Tables** tab holds a property that specifies the default primary key column for all of the content tables (as opposed to object tables) in your WebCenter Sites database.

If you or your developers create any content tables to support your online sites, you can specify that a column other than the one specified by the default is the primary key column for those content tables by creating table-specific properties. Use the following format:

```
cc.<name of table>Key=<name of column>
```

For example, when WebCenter Sites installs the `Category` table (which is used by basic asset types), it creates a property named `cc.CategoryKey`. The `cc.CategoryKey` property and any new property that you create appears on the **User Defined** tab rather than the **Content Tables** tab.

Caution

Do not change the key value specified for any of the WebCenter Sites content tables.

The following table describes the content tables property:

Properties in `futuretense.ini`: **Content Tables Tab**

Property	Descriptions
<code>cc.contentkey</code>	<p>Specifies the name of the column that serves as the primary key for content tables in the WebCenter Sites database. This is a default setting that applies to any content table that does not have a table-specific property that sets a different primary key for it.</p> <p>Value set during installation of the WebCenter Sites content applications: <code>id</code></p> <p>Caution: Do not change the value of this property. If you change it, the WebCenter Sites content applications will not function.</p> <p>To specify a different primary key for an individual content table, create a table-specific key property as described in the paragraphs preceding this table.</p>

futuretense.ini: Database Tab

The **Database** tab holds both the general database configuration properties such as database name and user access properties, and vendor-specific properties such as how the database interprets date/time values.

Database properties must be set to the same values on each of the systems in your WebCenter Sites system—development, management, and delivery—so that you can move assets and other work from one system to another.

Note

Database properties are set during the WebCenter Sites installation process. If you need assistance with determining property values or setting them during the installation process, contact Oracle Technical Support. Do **not** change the values of these properties after WebCenter Sites is installed.

If you are unsure about how property values were determined, check with your database administrator or the individual who installed WebCenter Sites.

Properties in futuretense.ini: Database Tab

Property	Description
cc.bigint	<p>Specifies the SQL string for defining a 64-bit integer field.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • Oracle: NUMBER(38) • SQL Server: BIGINT • DB2: BIGINT <p><i>See also</i> the note above this table.</p>
cc.bigtext	<p>Specifies the SQL string for defining a large text field.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • Oracle: CLOB • SQL Server: TEXT • DB2: LONG VARCHAR <p><i>See also</i> the note above this table.</p>
cc.blob	<p>Specifies the SQL string for defining a BLOB (binary large object) field.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • Oracle: BLOB • SQL Server: IMAGE • DB2: LONG VARCHAR FOR BIT DATA <p><i>See also</i> the note above this table.</p>

Properties in futuretense.ini: **Database Tab** (continued)

Property	Description
cc.char	<p>Specifies the SQL string for defining a CHAR data type.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • Oracle: CHAR • SQL Server: CHAR • SQL Server, multi-lingual Unicode: NCHAR • DB2: CHAR <p><i>See also</i> the note above this table (page 65).</p>
cc.datepicture	<p>Specifies how WebCenter Sites creates a date/time literal.</p> <p>Default value: {ts '\$date'}</p> <p><i>See also</i> the note above this table (page 65).</p>
cc.datetime	<p>Specifies the SQL string for defining a date/time field.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • Oracle 8: DATE • Oracle 9: TIMESTAMP • SQL Server: DATETIME • DB2: TIMESTAMP <p><i>See also</i> the note above this table (page 65).</p>
cc.double	<p>Specifies the SQL string for defining a double field.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • Oracle: NUMBER(38,10) • SQL Server: NUMERIC(28,10) • DB2: FLOAT <p><i>See also</i> the note above this table (page 65).</p>
cc.forcelower	<p>Specifies whether the column names for the tables that WebCenter Sites creates have all lowercase letters.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • Oracle: true • SQL Server: false • DB2: true <p><i>See also</i> the note above this table (page 65).</p>

Properties in futuretense.ini: Database Tab (continued)

Property	Description
cc.ignoreTblCase	<p>Determines whether WebCenter Sites ignores case when assessing table names.</p> <p>Possible values: yes no</p> <p>For example, if “tablename” and “TABLENAME” would be considered different tables in your database, set this value to no.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • Oracle: yes • SQL Server: yes • DB2: yes <p><i>See also</i> the note above this table (page 65).</p>
cc.integer	<p>Specifies the SQL string for defining a 32-bit integer field.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • Oracle: NUMBER (10) • SQL Server: INT • DB2: INTEGER <p><i>See also</i> the note above this table (page 65).</p>
cc.maxvarcharsize	<p>Specifies the maximum size of a varchar column for your database.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • Oracle: 2000 • SQL Server: 8000 • DB2: 4000 <p><i>See also</i> the note above this table (page 65).</p>
cc.null	<p>Specifies the SQL string for defining a field which allows NULL values; this is nonstandard, though most databases support NULL.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • Oracle: NULL • SQL Server: NULL • DB2: blank <p><i>See also</i> the note above this table (page 65).</p>

Properties in futuretense.ini: Database Tab (continued)

Property	Description
cc.numeric	<p>Specifies the SQL string for defining a numeric field.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • Oracle: NUMBER • SQL Server: NUMERIC • DB2: NUMERIC <p><i>See also</i> the note above this table (page 65).</p>
cc.primary	<p>Specifies the SQL string that defines a primary key.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • Oracle: PRIMARY KEY NOT NULL • SQL Server: PRIMARY KEY NOT NULL • DB2: PRIMARY KEY NOT NULL <p><i>See also</i> the note above this table (page 65).</p>
cc.queryablemaxvarcharlength	<p>Specifies the maximum size of a varchar column that can be queried based on the database driver in use.</p> <ul style="list-style-type: none"> • Oracle Thin: 255 • Oracle TypeII: 2000 • SQL Server: 255 • DB2: 255
cc.rename	<p>Specifies the SQL string that renames a table in the database, as required by your database vendor.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • Oracle: rename %1 to %2 • SQL Server: execute sp_rename %1,%2 • DB2: rename %1 to %2 <p><i>See also</i> the note above this table (page 65).</p>
cc.smallint	<p>Specifies the SQL string for defining a 16-bit integer field.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • Oracle: NUMBER (5) • SQL Server: SMALLINT • DB2: SMALLINT <p><i>See also</i> the note above this table (page 65).</p>

Properties in futuretense.ini: **Database Tab** (continued)

Property	Description
cc.stringpicture	<p>Specifies how WebCenter Sites creates a string literal.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • Oracle: '\$string' • SQL Server: '\$string' • SQL Server, multi-lingual Unicode: N '\$string' • DB2: '\$string' <p><i>See also</i> the note above this table (page 65)</p>
cc.unique	<p>Specifies the SQL string for defining a unique field.</p> <p>Possible values:</p> <ul style="list-style-type: none"> • Oracle: UNIQUE NOT NULL • SQL Server: UNIQUE NOT NULL • DB2: UNIQUE NOT NULL <p><i>See also</i> the note above this table (page 65).</p>
cc.varchar	<p>Specifies the SQL string for defining a VARCHAR data type.</p> <p>Possible values: VARCHAR, for all supported databases except SQL Server, multi-lingual Unicode which is set to NVARCHAR</p> <p><i>See also</i> the note above this table (page 65)</p>
cs.dbconnpicture	<p>Specifies the format of the database connection string used by JNDI datasources:</p> <p><i>See also</i> the note above this table (page 65).</p>
cs.dbtype	<p>Defines the type of database to which you are connecting.</p> <p><i>See also</i> the note above this table (page 65)</p>
cs.dsn	<p>Contains the database JNDI data source name for connecting to your database.</p> <p><i>See also</i> the note above this table (page 65)</p>
cs.privpassword	<p>Specifies the password for the database account name used for read/write access (cs.privuser). The value is encrypted.</p>

Properties in `futuretense.ini`: **Database** Tab *(continued)*

Property	Description
<code>cs.privuser</code>	<p>Specifies the database account name to use for read/write access to the database. For security reasons, be sure that your system is not using the default user name/password combination.</p> <p>Default value: <code>ftuser</code> (set during installation)</p>

futuretense.ini: Debug Tab**Note**

For information about enabling debug logging, see “[commons-logging.properties](#)” on page 20. See also “Error Logging and Debugging” in the *WebCenter Sites Developer’s Guide*.

If you enable debug logging, note the following:

- Delete or archive the WebCenter Sites log file frequently, because a large log file can affect WebCenter Sites performance.
- By default, all debug log messages go into a single log file, which can make debugging more difficult. To place debug messages into a separate log file, set the `logging.per-client-log` property to `true`. The property is defined on [page 31](#).

Properties in futuretense.ini: Debug Tab

Property	Description
<code>ft.debugport</code>	<p>Deprecated. Specifies the port that DebugServer uses to communicate with the template debugger utility. The port number must be greater than 1024.</p> <p>Default value: 1025</p>
<code>ft.suppressPasswords</code>	<p>Prevents any input or session variables containing the strings "password" or "PASSWORD" in their names from being logged.</p> <p>Default value: true</p> <p>Specify false to include passwords in the log.</p>
<code>ft.suppressPasswordNames</code>	<p>Specifies variable names that are used as passwords and should be suppressed when <code>ft.suppressPasswords</code> is set to true.</p> <p>The Cheetah installer now sets this property to: <code>REMOTEPASS;pubtgt:factors;factors</code> to suppress its mirror publish target passwords in the log.</p>

futuretense.ini: Email Tab

The **Email** tab holds the properties that configure the WebCenter Sites e-mail system features. Note that in `futuretense_xcel.ini`, an additional property, `xcelerate.emailnotification`, on the **Preference** tab enables the WebCenter Sites workflow e-mail system to send notices to workflow participants when they are assigned assets through a workflow process.

Properties in `futuretense.ini`: **Email Tab**

Property	Description
<code>cs.emailaccount</code>	Specifies the user account name to be used for sending outgoing mail. This is the account name on the SMTP server. If SMTP authentication is required, you must set a value for this property.
<code>cs.emailauthenticator</code>	Specifies the class that is used as the authenticator for mail operations. Default value: <code>com.openmarket.framework.mail.ICSAuthenticator</code>
<code>cs.emailcharset</code>	Specifies the default character set that is used for the text in the subject of an e-mail message. Examples: <ul style="list-style-type: none"> • Latin1: <code>ISO-8859-1</code> • Japanese (Shift_JIS): <code>Shift_JIS</code> • UTF-8: <code>UTF-8</code> If this property is blank, its value reverts to the default UTF-8.
<code>cs.emailcontenttype</code>	Specifies the default character set that is used for the text in the body of an e-mail message. Examples: <ul style="list-style-type: none"> • Latin1: <code>text/html; charset=ISO-8859-1</code> • Japanese (Shift_JIS): <code>text/html; charset=Shift_JIS</code> • UTF-8: <code>text/html; charset=UTF-8</code> If this property is blank, its value reverts to the default <code>text/plain</code> .
<code>cs.emailhost</code>	Defines the SMTP (e-mail server) host that is used by the ContentServer servlet to create and deliver e-mail messages. A valid value is required to send or receive mail.

Properties in `futuretense.ini`: **Email Tab** (*continued*)

Property	Description
<code>cs.emailpassword</code>	<p>Specifies the password for the e-mail account used by WebCenter Sites (specified by <code>cs.emailaccount</code>).</p> <p>A valid value is required to receive mail.</p>
<code>cs.emailreturnto</code>	<p>Specifies the e-mail address from which mail is sent. That is, the e-mail address that appears in the From field of an e-mail message.</p> <p>Use one of the following formats:</p> <p><code>user@domain.com</code> <code>Full Name <user@domain.com></code></p> <p>A valid value is required to send mail.</p>

futuretense.ini: Export/Mirror Tab

The **Export/Mirror** tab holds the properties that configure the WebCenter Sites Export and Mirror APIs used by the WebCenter Sites publishing system. These properties work in conjunction with the properties located on the **Publishing** tab in the [futuretense_xcel.ini](#) file.

When configuring publishing operations for your WebCenter Sites systems, think of your individual systems (development, management, delivery) in the following terms:

- **Source**, which denotes the WebCenter Sites database that is the source for a publishing session. Because you can mirror assets and site configuration information from any WebCenter Sites system to any other WebCenter Sites system, the source is not necessarily the WebCenter Sites management system.
- **Target**, which denotes either the WebCenter Sites database to which you are mirroring, or the file server to which are exporting.

For more information about publishing, see the *WebCenter Sites Administrator's Guide*

Properties in futuretense.ini: Export/Mirror Tab

Property	Description
cs.mirrorhttpversion	Specifies the HTTP protocol version to use to communicate with the WebCenter Sites target databases. Default value: 1
cs.mirrorpassword	Specifies the password for the mirror user on the target systems to which this system publishes. You set this value when you set up your WebCenter Sites system for publishing. For information, see the <i>WebCenter Sites Administrator's Guide</i> .
cs.mirrorproxyserver	Specifies the firewall server's IP address or name for the target system that this (source) system publishes to when the target and the source are separated by a firewall. You set this value when you set up your WebCenter Sites system for publishing. Possible values: your_server_name or your_server_ip_address For information, see the <i>WebCenter Sites Administrator's Guide</i> .

Properties in futuretense.ini: **Export/Mirror** Tab (continued)

Property	Description
cs.mirrorproxyserverport	<p>Specifies the port number of the firewall server for the WebCenter Sites system that this system publishes to when the target system is separated from the source with a firewall. You set this value when you set up your WebCenter Sites system for publishing.</p> <p>Possible values: port_number</p> <p>For information, see the <i>WebCenter Sites Administrator's Guide</i>.</p>
cs.mirrorrowsperpost	<p>Specifies the number of table rows that can be mirrored during each HTTP POST during a mirror operation</p> <p>If you are mirroring data that contains URL fields, you should set this to a low number because web servers impose a limit on the size of post packets.</p> <p>If you are mirroring data that contains only text, you can set this to a higher number.</p> <p>Default value: 6</p> <p>Note: For best performance, do not increase the value above 12. If your database is configured for UTF-8 and holds non-ASCII content, you must set this value to 4 or lower.</p>
cs.mirrorthreads	<p>Specifies the number of threads to allocate to a mirror operation.</p> <p>Default value: 2</p> <p>Note: For best performance, do not increase the value above 8.</p>
cs.mirroruser	<p>Specifies the name of the mirror user on the target system that this (source) system publishes to. You set this value when you set up your system for publishing.</p> <p>For information, see the <i>WebCenter Sites Administrator's Guide</i>.</p>
cs.pgexportfolder	<p>Specifies the base export directory for the HTML files that are created when assets are published with the Export to Disk delivery type.</p> <ul style="list-style-type: none"> Windows NT example: c:/FutureTense/export Solaris example: /export/home/FutureTense/pgexport

futuretense.ini: JSP Tab

The **JSP** tab holds the properties that supply information that WebCenter Sites references when serving JavaServer Pages files.

Properties in `futuretense.ini`: **JSP Tab**

Property	Description
<code>cs.jspclear</code>	<p>Configures the WebCenter Sites engine to delete any previously deployed JSP files and clear the application server's working folder (temp and class files) when the WebCenter Sites engine executes the first JSP deployed by WebCenter Sites.</p> <p>The working folder is defined by the application server.</p> <p>Possible values: <code>true</code> <code>false</code></p>
<code>cs.jspspath</code>	<p>Specifies the virtual root (zone) for executing deployed JSP pages. This property is used in conjunction with <code>cs.jsproot</code>, so the two properties must be in sync.</p> <p>Default value: <code>synchronized</code> with the WebLogic setting for <code>cs.jsproot</code> and is set at installation.</p> <p>Note: Do not change the value of this property after installation.</p>
<code>cs.jsprefresh</code>	<p>When the WebCenter Sites engine deploys a new or changed JSP element, the application server may require special processing to complete the deployment of the JSP. In those cases, this property specifies the name of the class which completes the deployment. In other cases, it is left blank.</p>
<code>cs.jspresponsewrapper</code>	<p>Specifies whether the application server requires the <code>PrintWriter</code> when it runs a JSP element. The WebCenter Sites installation sets this to an appropriate value based on the type of application server you are using.</p> <p>Do not change the value of this property.</p>

Properties in `futuretense.ini`: **JSP Tab** (continued)

Property	Description
<code>cs.jsproot</code>	<p>Specifies the directory where the application server expects to find JSP files. Some application servers allow this value to be modified by using property settings. WebLogic defines <code>weblogic.httpd.initArgs</code> for its JSPServlet object.</p> <p>The <code>cs.jsproot</code> property is used in conjunction with <code>cs.jsppath</code>, so the two must be in sync and both are set at installation.</p> <p>Do not change the value of this property after installation.</p>
<code>cs.jspwork</code>	<p>Specifies the directory where class files are created by the application server when executing JSP pages. This is not a required property and can be left blank, but it is normally set at installation.</p> <p>For more information, see <code>cs.jspclear</code>.</p>
<code>cs.use.short.jsp.names</code>	<p>Some file systems impose a limit on the length of absolute paths. Using long JSP names on such file systems can result in file system errors.</p> <p>If you are using such a file system, set this property to <code>true</code> to use shortened JSP names.</p> <p>When this property is set to <code>false</code>, the JSP name will correspond to the element name.</p> <p>This property is set automatically by the WebCenter Sites installer; it should be changed only when absolutely necessary.</p> <p>Default value: <code>false</code></p>

futuretense.ini: Misc Tab

The **Misc** tab holds miscellaneous properties such as the amount of idle time a connection can have before WebCenter Sites logs out of a connection and whether WebCenter Sites loads cache synchronization processing.

Properties in `futuretense.ini`: **Misc Tab**

Property	Description
<code>cs.charset</code>	<p>Specifies a variable that can be included in HTML forms as a hidden variable. The variable, which gets set by the browser, specifies the text encoding of the form data that WebCenter Sites must process.</p> <p>Default value: <code>_charset_</code></p> <p>Do not change the value of this property.</p>
<code>cs.contenttype</code>	<p>Specifies the default character set to use for HTTP headers (streaming text).</p> <p>Default value: <code>text/html; charset=UTF-8</code></p> <p>Specify a value that is appropriate for the online site that your WebCenter Sites system is delivering.</p> <p>Examples:</p> <ul style="list-style-type: none"> • Latin1: <code>text/html; charset=ISO-8859-1</code> • Japanese (Shift_JIS): <code>text/html; charset=Shift_JIS</code>
<code>cs.disksize</code>	<p>Specifies the size limit in bytes for keeping uploaded files in memory while they are being posted. If an uploaded file is larger than the value specified, WebCenter Sites streams it to a temporary file until it is finished evaluating a page. This prevents excessive memory use and helps to prevent denial-of-service attacks.</p> <p>Default value: <code>102400</code></p>
<code>cs.documentation</code>	<p>Specifies the URL of the WebCenter Sites documentation.</p> <p>By default, this property is set to an Oracle documentation web site.</p> <p>If you prefer, you can download the most recent documentation kit from that web site, install it somewhere on your network, and then set this property to point to that location rather than to the Oracle documentation web site.</p>

Properties in futuretense.ini: **Misc Tab** (continued)

Property	Description
<code>cs.HTTP_HOST</code>	<p>Specifies the HTTP host for WebCenter Sites systems on which the web server does not reside on the application server machine (that is, it is a web connector installation), or in cases where an alternative web server is used to serve pages.</p> <p>Use one of the following formats:</p> <p><hostname>:<port> <IPAddress>:<port></p> <p>Default value: blank</p>
<code>cs.HTTP_PROTOCOL</code>	<p>Specifies the HTTP protocol for WebCenter Sites systems where the web server does not reside on the application server machine (that is, it is a web connector installation), or in cases where an alternative web server is used to serve pages.</p> <p>Possible values: http or https or blank</p> <p>Default value: blank, which means the protocol is assumed to be http</p>

Properties in futuretense.ini: **Misc Tab** (continued)

Property	Description
cs.sitepreview	<p>This property is used to control the behavior of Site Preview functionality. The value of this property determines the output of the filter tag (<code>asset:filterassetsbydate</code>) as explained below.</p> <p>Note: To use Site Preview on a content management environment, you must set this property to <code>contentmanagement</code>.</p> <p>Possible values: <code>disabled</code>, <code>contentmanagement</code>, <code>delivery</code></p> <ul style="list-style-type: none"> • If the value is set to <code>disabled</code>: <ul style="list-style-type: none"> - The filter tag will not filter. It will simply return the set of input assets. - Caching will not factor in start/end dates in the expiry time calculations. Date inputs to the templates will have no effect. • If the value is set to <code>contentmanagement</code>: <ul style="list-style-type: none"> - The filter tag will filter the input set of assets according to the given date. If the given date is null, the tag will use the current server date. - Pages whose rendering templates use the filter tag will not be cached. - For pages that do not use the filter tag, caching will work in the default manner and expiry time calculations will not factor in start/end dates. • If the value is set to <code>delivery</code>: <ul style="list-style-type: none"> - The filter tag will ignore all dates passed to it and will use the current server date for filtering. - For pages that use the filter tag, caching will factor in start/end dates in the expiry time calculation. - For pages that do not use the filter tag, caching will work in the default manner and expiry time calculations will not factor in start/end dates. <p>Default value: <code>disabled</code></p>

Properties in futuretense.ini: **Misc Tab** (continued)

Property	Description
cs.urlfilerollup	<p>Determines how changes to the files for URL columns are tracked.</p> <p>When this property is set to <code>true</code>, the previous versions of the related file are tracked in a name sequence. For example, if a file called <code>filename.txt</code> has been edited three times, <code>filename.txt</code> is the oldest, <code>filename,1.txt</code> is the next oldest version, and <code>fsilename,2.txt</code> is the current version.</p> <p>When this property is set to <code>false</code>, the file name toggles between <code>filename.txt</code> and <code>filename,0.txt</code> on alternate updates.</p>
cs.xmlfolder	<p>Specifies the working directory for HTML filtering. That is, if elements on your system use the <code>XMLFILTER</code> tag, temporary files are written to this directory.</p> <p>Default value: <code>\$HOME/FutureTense/xmltemp</code></p>
cs.xmlHeader	<p>This is the XML Header streamed out for SOAP responses.</p>

futuretense.ini: Page Cache Tab

The **Page Cache** tab holds the properties that configure WebCenter Sites' page cache settings. WebCenter Sites' page cache is monitored and maintained by the CacheManager. WebCenter Sites caching enables you to cache both complete web pages and their individual components (or pagelets).

To set up page caching on a WebCenter Sites system, you configure properties for the CacheManager and the Satellite Server servlets. In addition, there are properties for configuring BlobServer, the servlet that serves blobs and caches blobs both through WebCenter Sites and the Satellite servlet.

For more information:

- Page caching – see the page caching chapter in the *WebCenter Sites Developer's Guide*. This chapter describes how WebCenter Sites' Cache Manager, the Satellite servlets, and the BlobServer servlet interact and work together.
- Satellite Server properties – see [“Satellite Server Tab”](#) on page 90 and [“satellite.properties”](#) on page 143.
- Resultset caching properties – see [“ResultSet Cache Tab”](#) on page 86.
- BlobServer properties – see [“Blob Server Tab”](#) on page 58.

Properties in futuretense.ini: Page Cache Tab

Property	Description
<code>cs.alwaysusedisk</code>	<p>Specifies the default cache setting for page entries in the <code>SiteCatalog</code> table that have no information in their <code>cacheinfo</code> column.</p> <p>If set to <code>yes</code>, then each page served from WebCenter Sites is cached to disk (the database), unless the value in that page entry's <code>cacheinfo</code> column specifies that it not be cached.</p> <p>Default value: <code>no</code></p>
<code>cs.expireonly</code>	<p>Controls how outdated pages are expunged from the cache.</p> <p>When this property is set to <code>false</code>, pages that need to be expunged from the cache are deleted immediately and synchronously, that is, the user must wait until all pages are deleted.</p> <p>When this property is set to <code>true</code>, pages that need to be expunged from the cache are marked for deletion, taken out of service, and then deleted at a later time by a cache cleanup event.</p> <p>Default value: <code>true</code></p> <p>Possible values: <code>true</code> <code>false</code></p>

Properties in futuretense.ini: **Page Cache Tab** (continued)

Property	Description
<code>cs.freezeCache</code>	<p>Specifies whether a cache maintenance event should regularly remove expired pages from the cache, or whether the expiration date of a page should be checked only when that page is requested.</p> <p>Set the value to yes if you do not want an event to regularly remove expired pages from the cache.</p> <p>Default value: <code>no</code></p>
<code>cs.IItemList</code>	<p>Defines the file that is used for the <code>ItemList</code> interface that is used by the Cache Manager.</p> <p>The <code>IItemList</code> interface is used to record compositional dependencies in the page cache. When this property is set to a legal class, dependency items will be recorded against a page id in the <code>SystemItemCache</code> table. This enables <code>CacheManager</code>. An illegal value results in <code>CacheManager</code> having no effect.</p> <p>Default value: <code>com.openmarket.xcelerate.publish.MyItemList</code></p> <p>Note: The default value is provided for reference only. Do not change the value of this property.</p>
<code>cs.manage.expired.blob.inventory</code>	<p>Controls whether the <code>CacheServer</code> servlet removes blobkey/compositional dependency mappings from the <code>SystemItemCache</code> table after the blobs expire from the local blobserver cache. (The <code>CacheServer</code> servlet is typically invoked every five minutes by the event engine.)</p> <p>Possible values: <code>true false</code></p> <ul style="list-style-type: none"> <code>true</code> disables the <code>CacheServer</code> servlet from removing blobkey/compositional dependency mappings from the <code>SystemItemCache</code> table when the blobs expire. <code>false</code> enables the <code>CacheServer</code> servlet to remove expired blob references from the <code>SystemItemCache</code> table when the blobs expire. <p>Default value: <code>false</code> (to support backward compatibility)</p> <p>Note: How this property takes effect depends on the value of the <code>bs.bCacheTimeout</code> property. (See page 58.)</p>

Properties in futuretense.ini: **Page Cache Tab** (continued)

Property	Description
<code>cs.nocache</code>	<p>Provides you with the ability to disable all disk-based page caching (pages will still be cached in memory). Use this property to temporarily shut down page caching when you are debugging your site, but do not leave this value set to <code>true</code> on a live system.</p> <p>Default value: <code>false</code></p>
<code>cs.pgCacheTimeout</code>	<p>Specifies the number of minutes that a page will exist in the page cache. A value of 0 (zero) disables timeout, which means pages never expire. However, no matter what the setting for this property, CacheManager refreshes a cached page if the publishing system reports that it published any of the assets on that page.</p> <p>Note: For CacheManager to work properly, this property must be set to 0. Otherwise, pages will expire, making it impossible for CacheManager to remove the corresponding entries from the Satellite Server cache, and users will view stale data.</p> <p>Default value: <code>0</code></p>
<code>cs.recordBlobInventory</code>	<p>Allows users to work with blob dependencies. To record blobs inventory, set the value of this property to <code>true</code>.</p>
<code>cs.requiresessioncookies</code>	<p>Specifies whether session ID information can be held in cookies or whether WebCenter Sites must encode session data into the links.</p> <p>Set to <code>true</code> (the default) if WebCenter Sites expects session cookies to be enabled. This allows all pages to be cached and does not encode the session id into any links. A value of <code>false</code> enables URL rewriting, with a negative effect on page caching performance.</p> <p>Default value: <code>true</code></p>
<code>cc.BlobServerTimeout</code>	<p>Specifies the default lifetime (in minutes) of a cached blob in memory. If memory is at a premium, you may reduce the value of this property.</p> <p>Default value: <code>1440</code> (that is, 24 hours)</p>

Properties in futuretense.ini: **Page Cache Tab** *(continued)*

Property	Description
<code>cc.BlobServerCacheCSz</code>	<p>Specifies the maximum number of blobs that will be cached in memory. If memory is at a premium, you may reduce the value of this property.</p> <p>Default value: 1000</p>
<code>cc.SystemPageCacheTimeout</code>	<p>Specifies the number of minutes a cached page is held in memory (cached pages are cached both to disk and to memory).</p> <p>Default value: 1440 (that is, 24 hours)</p>
<code>cc.SystemPageCacheCSz</code>	<p>Specifies the maximum number of pages that can be cached in memory. Pages are cached both in memory and to disk (database). This property specifies the number of pages cached to memory, not to disk.</p> <p>Note: This property must not be set to -1.</p> <p>Default value: 10000</p>
<code>ss.flushall</code>	<p>Controls how Satellite Server cache is flushed.</p> <p>When this property is set to <code>false</code> (default), only outdated pagelets are flushed from the Satellite Server cache.</p> <p>When this property is set to <code>true</code>, the Satellite Server cache is flushed completely (when a single asset is updated).</p> <p>Default value: <code>false</code></p> <p>Possible values: <code>true</code> <code>false</code></p>

futuretense.ini: ResultSet Cache Tab

The **ResultSet Cache** tab holds properties that configure WebCenter Sites' resultset caching. For information about resultset caching and queries on your WebCenter Sites system, see the *WebCenter Sites Developer's Guide*.

The **ResultSet Cache** tab holds the following properties:

- Global resultset caching properties, which are set during the WebCenter Sites installation process to enable resultset caching for *all* tables in the WebCenter Sites database. The same properties will be automatically applied to all tables that are subsequently created. The properties are:
 - `cc.cacheResults`: number of resultsets to cache in memory
 - `cc.cacheResultsTimeout`: length of time to keep resultsets cached in memory
 - `cc.cacheResultsAbs`: method of calculating expiration time for resultsets in the resultset cache
- Table-specific resultset caching properties for system tables. These properties are automatically set during the WebCenter Sites installation process to override the global resultset caching properties named above.

For example, the following table-specific properties are set for the `ElementCatalog` table: `cc.ElementCatalogCSz` and `cc.ElementCatalogTimeout`. The property values can be changed, or the properties can be removed (the resultset cache for the table will then use the values of the global properties).

Note

If you wish to override global resultset caching properties, you must do so on a per-table basis by creating the following table-specific properties in the `futuretense.ini` file for as many tables as necessary to implement your resultset caching strategy for each of your WebCenter Sites systems:

```
cc.<tablename>CSz=<number of resultsets>
cc.<tablename>Timeout=<number of minutes>
cc.<tablename>Abs=<true or false>
```

If an asset type is enabled for revision tracking, and you wish to cache the resultsets of asset versions, use the properties above, but add `_t` after `<tablename>`:

```
cc.<tablename>_tCSz=<number of resultsets>
cc.<tablename>_tTimeout=<number of minutes>
cc.<tablename>_tAbs=<true or false>
```

When you create resultset caching properties that are specific for any *user-defined* table in the WebCenter Sites database, those properties are displayed on the **User Defined** tab (described on [page 92](#)).

For information about page caching properties, see [“Page Cache Tab”](#) on page 82. For information about BlobServer caching properties, see [“Blob Server Tab”](#) on page 58.

Note

WebCenter Sites stores resultsets within the inCache framework instead of hash tables. Both caching frameworks use Java memory. You can switch between frameworks by setting the `rsCacheOverinCache` property in `futuretense.ini` to either `true` or `false`. For more information, see [rsCacheOverinCache](#), on page 96.

The following table describes properties on the **ResultSet Cache** tab.

Properties in `futuretense.ini`: **ResultSet Cache** Tab

Property	Description
<code>cc.cacheResults</code>	<p>Specifies the default number of resultsets to cache in memory. Note that this does not mean the number of records in a resultset, but the number of resultsets.</p> <p>Caution: Unless you are debugging, do not set this property to 0 or -1. If you do, the WebCenter Sites interface will fail to save assets properly. (Setting this property to 0 or -1 disables resultset caching for all tables that do not have their own caching properties configured.)</p> <p>Possible values: <n> (number of resultsets)</p> <p>Default value: 500</p> <p>Note: To set a different value for a specific table, create a property for that table using the following format: <code>cc.<tablename>CSz=<number of resultsets></code></p>
<code>cc.cacheResultsAbs</code>	<p>Specifies how expiration time for resultsets in the resultset cache is calculated.</p> <ul style="list-style-type: none"> If this property is set to <code>true</code>, the expiration time for a resultset is absolute. For example, if <code>cc.cacheResultsTimeout</code> is set to 5 minutes, then 5 minutes after the resultset was cached, it is flushed from the cache. If this property is set to <code>false</code>, the expiration time for a resultset is based on its idle time. For example, if <code>cc.cacheResultsTimeout</code> is set to 5 minutes, the resultset is flushed from the cache 5 minutes after the last time it was requested rather than 5 minutes since it was originally cached. <p>Note: To set expiration time for a specific table, create a property for that table using the following format: <code>cc.<tablename>CAbs=<true or false></code></p>

Properties in futuretense.ini: **ResultSet Cache Tab** (continued)

Property	Description
<code>cc.cacheResultsTimeout</code>	<p>Specifies the number of minutes to keep a resultset cached in memory.</p> <p>Setting this property to -1 means that there is no timeout value for tables that do not have their own caching properties configured.</p> <p>Possible values: <n> (in minutes), or -1 to disable timeout for tables that use this default property.</p> <p>Default value: 5</p> <p>Note: To set timeout for a specific table, create a property for that table using the following format: <code>cc.<tablename>Timeout=<number of minutes></code></p>
<code>cc.ElementCatalogCSz</code>	<p>Specifies the number of resultsets to cache against the <code>ElementCatalog</code> table.</p> <p>For best performance this value should be set to the number of rows in the table.</p> <p>Default value: 1000</p>
<code>cc.ElementCatalogTimeout</code>	<p>Specifies the number of minutes to keep idle resultsets for the <code>ElementCatalog</code> table in the resultset cache.</p> <p>Use -1 to disable timeout.</p> <p>Default value: 60</p>
<code>cc.SiteCatalogCSz</code>	<p>Specifies the number of resultsets to cache against the <code>SiteCatalog</code> table.</p> <p>For best performance, this value should be set to the number of rows in the table.</p> <p>Default value: 1000</p>
<code>cc.SiteCatalogTimeout</code>	<p>Specifies the number of minutes to keep idle resultsets for the <code>SiteCatalog</code> table in the resultset cache.</p> <p>Use -1 to disable timeout.</p> <p>Default value: 60</p>
<code>cc.SystemACLCSz</code>	<p>Specifies the number of resultsets to cache against the <code>SystemACL</code> table.</p> <p>For best performance, this value should be proportional to the number of rows in the table.</p> <p>Default value: 25</p>

Properties in `futuretense.ini`: **ResultSet Cache Tab** (*continued*)

Property	Description
<code>cc.SystemACLTimeout</code>	<p>Specifies the number of minutes to keep idle resultsets for the <code>SystemACL</code> table in the resultset cache.</p> <p>Default value: -1 (which disables timeout for this table)</p>
<code>cc.SystemInfoCSz</code>	<p>Specifies the number of resultsets to cache against the <code>SystemInfo</code> table.</p> <p>For best performance, this value should be set to the number of rows in the table.</p> <p>Default value: 500</p>
<code>cc.SystemInfoTimeout</code>	<p>Specifies the number of minutes to keep idle resultsets for the <code>SystemInfo</code> table in the resultset cache.</p> <p>Default value: -1 (which disables timeout for this table)</p>
<code>cc.SystemUsersCSz</code>	<p>Specifies the number of resultsets to cache against the <code>SystemUsers</code> table.</p> <p>For best performance, this value should be proportional to the number of rows in the table.</p> <p>Default value: 100</p>
<code>cc.SystemUsersTimeout</code>	<p>Specifies the number of minutes to keep idle resultsets for the <code>SystemUsers</code> table in the resultset cache.</p> <p>Default value: -1 (which disables timeout for this table)</p>
<code>ft.filecheck</code>	<p>Specifies whether WebCenter Sites verifies the timestamp on data held in an upload field each time an item (like an element) with uploaded data is requested.</p> <p>On a management or delivery system, the same items are requested repeatedly and setting this value set to <code>yes</code> can slow the performance of the system. Set this property to <code>no</code> on management or delivery systems. You can set it to <code>yes</code> on a development system.</p> <p>Default value: <code>no</code></p>

futuretense.ini: Satellite Server Tab

The **Satellite Server** tab holds properties that describe how to communicate with any of the Satellite servlets (Satellite Server), whether they are running locally or on remote servers.

Additionally, because Satellite Server is installed by default on the server that hosts your WebCenter Sites application, each WebCenter Sites system also has a `satellite.properties` file that configures the local Satellite servlet. (Note that when Satellite Server is also running on a remote server, that server also has a `satellite.properties` file.) For information about the properties in that file, see [“satellite.properties”](#) on page 143.

The following table describes the properties on the server that hosts WebCenter Sites that support communications with all Satellite servlets.

The value for each property is a comma-separated list. The ordinal position of an item in the list is what associates the host, user name, and password for each Satellite servlet. For example, the third host named in `cs.satellitehosts` is accessed using the third user account named in `cs.satelliteusers`, giving the third password listed in `cs.satellitepassword`.

Properties in `futuretense.ini`: **Satellite Server Tab**

Property	Description
<code>cs.PastramiEngine</code>	Defines the name of the implementing class of the <code>PastramiEngine</code> interface. Leave this property null to disable this feature entirely. The standard value for this property is: <code>com.divine.pastrami.PushEngine</code>
<code>satellite.blob.cache control.default</code>	Specifies a default value for the <code>cachecontrol</code> parameter for the <code>satellite.blob</code> , and <code>RENDER.SATELLITEBLOB</code> tags and their JSP equivalents. Default value: blank Set this property to a value that is appropriate for the majority of your blobs, and then use the <code>cachecontrol</code> parameter with the <code>satellite.blob</code> and <code>RENDER.SATELLITEBLOB</code> tags to override this value for individual blobs. Use the following format to set a value: <code>hours:minutes:seconds daysOfWeek/ daysOfMonth/months</code> For more information about this format, see the description of the <code>expiration</code> property in the section “satellite.properties” on page 143.

Properties in futuretense.ini: **Satellite Server** Tab *(continued)*

Property	Description
<code>satellite.page.cache control.default</code>	<p>Deprecated.</p> <p>Specifies a default value for the <code>cachecontrol</code> parameter for the <code>satellite.page</code>, and <code>RENDER.SATELLITEPAGE</code> tags and their JSP equivalents.</p> <p>Default value: blank</p> <p>Set this property to a value that is appropriate for the majority of your pages and pagelets, and then use the <code>cachecontrol</code> parameter with the <code>satellite.page</code> and <code>RENDER.SATELLITEPAGE</code> tags to override this value for individual pages and pagelets.</p> <p>Use the following format to set a value:</p> <p><code><hours>:<minutes>:<seconds> <daysOfWeek>/<daysOfMonth>/<months></code></p> <p>For more information about this format, see the description of the <code>expiration</code> property in the section “satellite.properties” on page 143.</p>

futuretense.ini: Search Tab

Properties on the **Search** tab are deprecated and unsupported.

futuretense.ini: User Defined Tab

The **User Defined** tab displays custom properties, which are not created by the core WebCenter Sites product but are used by WebCenter Sites and its content applications.

This tab displays the following kinds of properties:

- Two custom properties for the sample site, if the WebCenter Sites portal sample site is installed.
- Properties that specify the name of the primary key column for a content table (catalog). For information about content tables, see the “Data Design” section in the *WebCenter Sites Developer’s Guide*.
- Custom properties that specify resultset caching settings for individual user-defined tables in the WebCenter Sites database. For more information, see the note in “[ResultSet Cache Tab](#)” on page 86.
- Custom properties that specify resultset caching settings for revision-tracked, user-defined tables in the WebCenter Sites database. For more information, see the note in “[ResultSet Cache Tab](#)” on page 86.

The following table lists all of the properties that any of the WebCenter Sites products create in the `futuretense.ini` file, which means that they appear on the **User Defined** tab. Note that your system may have additional properties that are not included in this list.

Properties in `futuretense.ini`: **User Defined Tab**

Property	Description
<code>analysisconnector.version</code>	<p>Deprecated.</p> <p>The version number of Analytics Bridge, if it is installed.</p> <p>Do not change the value of this property.</p>
<code>catalogcentre.version</code>	<p>Deprecated.</p> <p>The version number of CS-Direct Advantage, if it is installed. CS-Direct Advantage was named Catalog Centre in early versions of the product.</p> <p>Do not change the value of this property.</p>
<code>cc.AssetTypeCSz</code>	<p>The number of resultsets to cache against the <code>AssetType</code> table, an object table that is created by the WebCenter Sites installation.</p> <p>Default value: 50</p>

Properties in futuretense.ini: **User Defined Tab** (continued)

Property	Description
<code>cc.CategoryCSz</code>	The number of resultsets to cache against the Category table, an object table that the WebCenter Sites installation creates for asset types. Default value: 50
<code>cc.ComparatorsKey</code>	The primary key of the Comparator table, a content table that the WebCenter Sites installation creates to hold field comparator classes. Default value: name Do not change the value of this property.
<code>cc.FiltersKey</code>	Default value: name
<code>cc.MimeTypeKey</code>	The primary key of the MimeType table, a content table that the WebCenter Sites installation creates to store the mimetypes of the documents that it handles. Default value: mimetype Do not change the value of this property.
<code>cc.PreviewgenKey</code>	Default value: name
<code>cc.SourceKey</code>	The primary key of the Source table, a content table that the WebCenter Sites installation creates for asset types. Default value: source Do not change the value of this property.
<code>cc.StatusCodeCSz</code>	The number of resultsets to cache against the StatusCode table, a content table that the WebCenter Sites installation creates for asset types. Default value: 10
<code>cc.StatusCodeKey</code>	The primary key of the StatusCode table. Default value: statuscode Do not change the value of this property.
<code>commerceconnector.version</code>	The version number of the Commerce Connector utility, if it is installed. Do not change the value of this property.

Properties in `futuretense.ini`: **User Defined Tab** (continued)

Property	Description
<code>contentcentre.version</code>	<p>Deprecated.</p> <p>The version number of CS-Direct, if it is installed. CS-Direct was named Content Centre in previous versions of the product.</p> <p>Do not change the value of this property.</p>
<code>cs.approvalLockStriping</code>	<p>Used to specify whether approval locking is</p> <ul style="list-style-type: none"> • global and default (<code>false</code>) or • per target (<code>true</code>), which prevents targets from competing for approval and publishing activities. Setting this property to <code>true</code> requires you to add a non-null column named <code>cs_target</code> to the <code>ApprovalQueue</code> table. The column's data type must match the value of the <code>cc.bigint</code> property (in <code>futuretense.ini</code>). <p>If you wish to switch back from approval locking per target to default behavior (i.e., global lock):</p> <ol style="list-style-type: none"> 1. Remove the <code>cs_target</code> column from the <code>ApprovalQueue</code> table. 2. Set <code>cs.approvalLockStriping</code> to <code>false</code> (or remove this property, as by default it is <code>false</code>).
<code>cs.parentfoldercount</code>	<p>Specifies the maximum number of parent folders that WebCenter Sites can generate in subdirectories of <code><cs_install_dir>/Shared</code>. Parent folders are the first level of numbered folders generated by WebCenter Sites. For example, if this property is set to 500, WebCenter Sites will generate no more than 500 parent folders in <code><cs_install_dir>/Shared/ccurl</code> (where flex assets are stored).</p> <p>If you wish to use this property, you must add it to <code>futuretense.ini</code>. If it is not added, WebCenter Sites uses the default value. Note that when this property is used, the existing parent folder structure remains as is. Parent folders that are no longer used will need to be deleted manually.</p> <p>Within the parent folders, WebCenter Sites generates child folders. If you wish to specify the maximum number of child folders that can be generated, use the <code>cs.childfoldercount</code> property (page 95).</p> <p>Default value: 1024</p>

Properties in `futuretense.ini`: **User Defined Tab** (continued)

Property	Description
<code>cs.childfoldercount</code>	<p>Specifies the maximum number of child folders that WebCenter Sites can generate in parent folders under subdirectories of <code><cs_install_dir>/Shared</code>. Child folders are numbered subfolders that WebCenter Sites generates inside the parent folders. For example, if this property is set to 300, WebCenter Sites will generate no more than 300 child folders in parent folders under <code><cs_install_dir>/Shared/ccurl</code>.</p> <p>If you wish to use this property, you must add it to <code>futuretense.ini</code>. If it is not added, WebCenter Sites uses the default value. Note that when this property is used, the existing child folder structure remains as is. Child folders that are no longer used will need to be deleted manually.</p> <p>If you also need to specify the maximum number of parent folders that WebCenter Sites can generate, use the <code>cs.parentfoldercount</code> property (page 94).</p> <p>Default value: 1024</p>
<code>cs.dbencoding</code>	<p>Default value: UTF-8</p>
<code>cs.invalMemWindow</code>	<p>This property applies to the inCache framework. It is used to define the size of the <code>FW_InvalidationMemory</code> table in terms of a data storage period, in seconds, for that table. The data storage period is a rolling window.</p> <p>For example, if the property is set to 20000, 20,000 seconds worth of data can be accumulated in the table. As additional data continues to arrive, it is stored, while data older than 20,000 seconds is purged by the table's cleanup mechanism. For more information about the inCache framework and <code>FW_InvalidationMemory</code> table, see the <i>WebCenter Sites Administrator's Guide</i>.</p> <p>If you wish to use this property, add it to the <code>futuretense.ini</code> file and set it to your required value. If the property is not added, WebCenter Sites uses the default value.</p> <p>Default value: 259200 (i.e., 3 days)</p>
<code>cs.requestfactory</code>	<p>Default value: <code>com.fatwire.cs.portals.portlet.PortletRequestFactory</code></p>
<code>ft.servletoutputstream</code>	<p>Default value: false</p>

Properties in futuretense.ini: **User Defined Tab** (continued)

Property	Description
image.time	Deprecated. Default value: 5:0:0 */*/*
marketingstudio.version	The version number of Engage. Do not change the value of this property.
page.time	Deprecated. Default value: *:0,5,10,15,20,25,30,35,40,45,50,55 :0 */*/*
propagatecache	Used to enable the propagation of pages among nodes that are enabled for the inCache page caching framework. Information about inCache can be found in the <i>WebCenter Sites Developer's Guide</i> .
rsCacheOverinCache	Used to switch between resultset caching media. This property is set to <code>true</code> by default, in which case WebCenter Sites caches resultsets in the inCache framework. When this property is set to <code>false</code> , WebCenter Sites caches resultsets in hash tables. Both caching media use the JVM memory. This property is set to <code>true</code> during the WebCenter Sites installation process. The process also completes following steps: <ul style="list-style-type: none"> Places the <code>linked-cache.xml</code> configuration file in the application server's classpath (<code>WEB-INF/classes</code> directory). Sets the following resultset caching properties (see "ResultSet Cache Tab" on page 86): <pre>cc.cacheResults cc.cacheResultsTimeout cc.cacheResultsAbs</pre> When the installation process is complete, the System Tools node (on the Admin tab of the Admin interface) displays the resultset over inCache tool, which provides statistical information about the caches and their contents.

Properties in futuretense.ini: **User Defined Tab** (continued)

Property	Description
rsCacheOverinCache (continued)	<p>Note: Resultset caching over inCache works independently of page and asset caching over inCache. Information about the inCache framework, its caching models and system tools is available in the <i>WebCenter Sites Administrator's Guide</i>. Additional information about resultset caching is also available in the <i>WebCenter Sites Developer's Guide</i>.</p> <p>Default value: true</p> <p>Possible values: true false</p>
soap.binaryRowsType	<p>A WebCenter Sites system property used to instantiate server-side objects in response to SOAP requests made by web services.</p> <p>Do not change the value of this property.</p>
soap.iList	<p>A WebCenter Sites system property used to instantiate server-side objects in response to SOAP requests made by web services.</p> <p>Do not change the value of this property.</p>
soap.likeConstraint	<p>A WebCenter Sites system property used to instantiate server-side objects in response to SOAP requests made by web services.</p> <p>Do not change the value of this property.</p>
soap.listRowsType	<p>A WebCenter Sites system property used to instantiate server-side objects in response to SOAP requests made by web services.</p> <p>Do not change the value of this property.</p>
soap.nestedConstraint	<p>A WebCenter Sites system property used to instantiate server-side objects in response to SOAP requests made by web services.</p> <p>Do not change the value of this property.</p>
soap.rangeConstraint	<p>A WebCenter Sites system property used to instantiate server-side objects in response to SOAP requests made by web services.</p> <p>Do not change the value of this property.</p>
soap.richTextConstraint	<p>A WebCenter Sites system property used to instantiate server-side objects in response to SOAP requests made by web services.</p> <p>Do not change the value of this property.</p>

Properties in futuretense.ini: **User Defined Tab** (continued)

Property	Description
<code>soap.searchstate</code>	A WebCenter Sites system property used to instantiate server-side objects in response to SOAP requests made by web services. Do not change the value of this property.
<code>soap.standardConstraint</code>	A WebCenter Sites system property used to instantiate server-side objects in response to SOAP requests made by web services. Do not change the value of this property.
<code>soap.stringRowsType</code>	A WebCenter Sites system property used to instantiate server-side objects in response to SOAP requests made by web services. Do not change the value of this property.
<code>soap.stringVarsType</code>	Default value: <code>com.openmarket.basic.objects.StringVarsType</code>
<code>soap.urlRowsType</code>	A WebCenter Sites system property used to instantiate server-side objects in response to SOAP requests made by web services. Do not change the value of this property.
<code>soap.URLType</code>	A WebCenter Sites system property used to instantiate server-side objects in response to SOAP requests made by web services. Do not change the value of this property.

futuretense_xcel.ini

Properties in `futuretense_xcel.ini` are organized by function on the following tabs in the Property Editor:

- [Analytics Tab](#)
- [Asset Default Tab](#)
- [Authorization Tab](#)
- [Debug Tab](#)
- [Directories Tab](#)
- [Element Override Tab](#)
- [Preference Tab](#)
- [Publishing Tab](#)
- [Transformer Tab](#)
- [xcelerate Tab](#)
- [User Management Tab](#)
- [User Defined Tab](#)

Note

WebCenter Sites also inserts custom properties into the “User Defined” tab in the `futuretense.ini` file, as described in [“futuretense.ini User Defined Tab”](#) on page 92.

futuretense_xcel.ini: Analytics Tab

The **Analytics** tab holds properties that are used to configure Oracle WebCenter Sites: Analytics. These properties are documented here in alphabetical order:

Properties in futuretense_xcel.ini: Analytics Tab

Property	Description
<code>analytics.datacaptureurl</code>	URL where the Analytics data capture servlet is running. Syntax: <code>http://<host>:<port>/sensor/statistic</code>
<code>analytics.enabled</code>	Indicates whether Analytics is installed. Legal values: <code>true</code> <code>false</code>
<code>analytics.piurl</code>	URL where the Analytics performance indicator servlet is running. Syntax: <code>http://<host>:<port>/analytics/PI</code>
<code>analytics.reporturl</code>	URL of the Analytics user interface. Syntax: <code>http://<host>:<port>/analytics/Report.do</code>
<code>analytics.user</code>	Pre-configured Analytics user who logs in to Analytics from WebCenter Sites. Default value: <code>csuser</code> Note: Changing the default name is not recommended.

futuretense_xcel.ini: Asset Default Tab

The **Asset Default** tab holds properties that are used to define certain default details about asset types, such as cache information, default ACLs, and whether CKEditor is present. These properties are documented here in alphabetical order:

Properties in futuretense_xcel.ini: Asset Default Tab

Property	Description
<code>xcelerate.asset.shareToAllAllowed</code>	Specifies whether the assets can be shared to all sites. Legal values: <code>true</code> <code>false</code>
<code>xcelerate.asset.sizeofnamefield</code>	Specifies the length of the Name field for basic and flex asset types. Default value: <code>64</code>
<code>xcelerate.body.length</code>	Specifies the number of characters that are stored for the Body field in the <code>Article</code> table in the <code>urlbody</code> column. Data entered in the Body field for an article asset (a sample site asset type) is written to the <code>urlbody</code> column. Because this is a URL column, that data is actually stored as a file outside of the WebCenter Sites database. However, the first <code><n></code> number of characters, where <code><n></code> equals the value specified for this property, is also stored in the <code>body</code> column so that you can search for text in the body of an article asset with the search feature in the WebCenter Sites interface. Default value: <code>1000</code> Maximum values: 256 for Windows NT or Windows 2000; 2000 for UNIX. If this property is missing or is not set, WebCenter Sites uses the value from the <code>cc.maxvarcharsize</code> property in the <code>futuretense.ini</code> file instead.
<code>xcelerate.defaultacl</code>	Specifies an ACL that is automatically assigned to page entries in the <code>SiteCatalog</code> table when they are created by the creation of <code>SiteEntry</code> or <code>Template</code> assets. Default value: <code>blank</code>
<code>xcelerate.defaultbase</code>	Specifies the default base of <code>defdir</code> for assets.

Properties in futuretense_xcel.ini: **Asset Default Tab** (continued)

Property	Description
xcelerate.default cscacheinfo	<p>Specifies the default value for the “Cache Rule (ContentServer)” field of SiteEntry and Template assets that are enabled for caching. The value is displayed when the Advanced caching option is selected; the value can be overridden.</p> <p>The “Cache Rule (ContentServer)” field maps to the cscacheinfo field in the SiteCatalog table, for each entry that corresponds to a SiteEntry asset or Template asset.</p> <p>Default value: true, ~0</p>
xcelerate.default sscacheinfo	<p>Specifies the default value for the “Cache Rule (Satellite)” field of SiteEntry and Template assets that are enabled for caching. The value is displayed when the Advanced caching option is selected; the value can be overridden.</p> <p>The “Cache Rule (Satellite)” field maps to the sscacheinfo field in the SiteCatalog table, for each entry that corresponds to a SiteEntry asset or Template asset.</p> <p>Default value: true, ~0</p>
xcelerate.default pagecriteria	<p>Specifies the default value for the pagecriteria column for page entries in the SiteCatalog table when they are created via a Template asset.</p> <p>Default value: c, cid, p, rendermode, site, context</p> <p>For definitions of these variables and for more information about page criteria variables in general, see the <i>WebCenter Sites Developer's Guide</i>.</p>
xcelerate.defaultcsstatus	<p>Specifies the default value for the csstatus column for page entries in the SiteCatalog table when they are created (for either Template or SiteEntry assets).</p> <p>Do not change the value of this property.</p> <p>Default value: live</p>
xcelerate.default pagecriteriaSite Entry	<p>Specifies the page criteria variables that can be set by default for SiteEntry assets. While you can add variables to this list, do not delete any of the default values.</p> <p>Default value: rendermode, site, seid, Sitepfx</p>

Properties in futuretense_xcel.ini: **Asset Default Tab** *(continued)*

Property	Description
xcelerate.ewebeditpro	Deprecated. Not supported. If your developers have designed asset types that use the eWebEditPro HTML editor, this property specifies the location of the ewebeditpro.js file.
xcelerate.MaxLinks	Specifies the number of links that could be included in a linkset, an old asset type that is no longer used.

futuretense_xcel.ini: Authorization TabProperties in futuretense_xcel.ini: **Authorization Tab**

Property	Description
xcelerate.authorize.functions	<p>Contains a comma-separated list of functions for which permissions can be generated on an asset. If the value is empty, all possible functions will be displayed. Additional system-defined functions can be added to the list of default functions.</p> <p>Default value: inspect, preview, checkout, copy, edit, delete, rollback, share, approve, build</p>
xcelerate.deny.abstainfromvoting	<p>Contains a comma-separated list of roles that are not allowed to abstain from voting when assigned assets as part of the workflow process.</p> <p>Default value: blank</p>
xcelerate.deny.approve	<p>Contains a comma-separated list of roles that are not allowed to approve assets for publishing.</p> <p>Default value: blank</p>
xcelerate.deny.authorize	<p>Contains a comma-separated list of roles that are not allowed to authorize privileges on assets.</p> <p>Default value: blank</p>
xcelerate.deny.build	<p>Contains a comma-separated list of roles that are not allowed to build Collection assets.</p> <p>Default value: blank</p>
xcelerate.deny.checkout	<p>Contains a comma-separated list of roles that are not allowed to checkout assets explicitly from the revision tracking system.</p> <p>Default value: blank</p>
xcelerate.deny.copy	<p>Contains a comma-separated list of roles that are not allowed to copy assets.</p> <p>Default value: blank</p>
xcelerate.deny.delegate	<p>Contains a comma-separated list of roles that are not allowed to delegate assigned assets to other participants in the workflow.</p> <p>Default value: blank</p>

Properties in futuretense_xcel.ini: **Authorization Tab** *(continued)*

Property	Description
xcelerate.deny.delete	Contains a comma-separated list of roles that are not allowed to delete assets. Default value: blank
xcelerate.deny.edit	Contains a comma-separated list of roles that are not allowed to edit assets. Default value: blank
xcelerate.deny.inspect	Contains a comma-separated list of roles that are not allowed to inspect assets. Default value: blank
xcelerate.deny.placepage	Contains a comma-separated list of roles that are not allowed to place assets in the SitePlan tree. Default value: blank
xcelerate.deny.preview	Contains a comma-separated list of roles that are not allowed to preview assets with their templates. Default value: blank
xcelerate.deny.remove fromgroup	Contains a comma-separated list of roles that are not allowed to remove assets from a workflow group. Default value: blank
xcelerate.deny.removefrom workflow	Contains a comma-separated list of roles that are not allowed to remove assets from workflow. Default value: blank
xcelerate.deny.rollback	Contains a comma-separated list of roles that are not allowed to roll back assets to a previous version. Default value: blank
xcelerate.deny.setExport Data	Contains a comma-separated list of roles that are not allowed to set export to disk (static publishing) starting point. These users may still be allowed to approve and publish assets if some other users set the starting point. Default value: blank

Properties in futuretense_xcel.ini: **Authorization Tab** (continued)

Property	Description
xcelerate.deny.set nestedworkflow	Contains a comma-separated list of roles that are not allowed to set nested workflow. Default value: blank
xcelerate.deny.set participants	Contains a comma-separated list of roles that are not allowed to set participants for workflow. Default value: blank
xcelerate.deny.set processdeadline	Contains a comma-separated list of roles that are not allowed to set workflow process deadlines. Default value: blank
xcelerate.deny.set stepdeadline	Contains a comma-separated list of roles that are not allowed to set a deadline on a workflow step. Default value: blank
xcelerate.deny.share	Contains a comma-separated list of roles that are not allowed to share assets with other sites (other than the site the asset was originally created in). Default value: blank
xcelerate.deny.show participants	Contains a comma-separated list of roles that are not allowed to see the participants that are set for a workflow. Default value: blank
xcelerate.deny.showstatus	Contains a comma-separated list of roles that are not allowed to see the status screen for assets. The status option shows up in more ... drop-down box of the inspect window. The screen shows workflow, publishing, and revision tracking information about the asset that is being inspected. If the user belongs to one of the roles that is being denied the privilege, the option to view the status screen will not show. Default value: blank

Properties in futuretense_xcel.ini: **Authorization Tab** (continued)

Property	Description
xcelerate.deny.show version	Contains a comma-separated list of roles that are not allowed to see the list of versions for an asset. Note: User can view the list of versions for an asset that is explicitly or implicitly checked out. The inspect form will not display a Show Versions button if the user belongs to one of the roles that is denied the privilege. Default value: blank
xcelerate.grant.abstain fromvoting	Contains a comma-separated list of roles that are allowed to abstain from voting when assigned assets as part of the workflow process. Default value: blank
xcelerate.grant.approve	Contains a comma-separated list of roles that are allowed to approve assets for publishing. Default value: blank
xcelerate.grant.authorize	Contains a comma-separated list of roles that are allowed to authorize privileges on assets. Default value: SparkAdmin, GeneralAdmin, WorkflowAdmin, SiteAdmin
xcelerate.grant.build	Contains a comma-separated list of roles that are allowed to build Collection assets. Default value: blank
xcelerate.grant.checkout	Contains a comma-separated list of roles that are allowed to checkout assets explicitly from the revision tracking system. Default value: blank
xcelerate.grant.copy	Contains a comma-separated list of roles that are allowed to copy assets. Default value: blank
xcelerate.grant.delegate	Contains a comma-separated list of roles that are allowed to delegate assigned assets to other participants in the workflow. Default value: blank

Properties in futuretense_xcel.ini: **Authorization Tab** (continued)

Property	Description
xcelerate.grant.delete	Contains a comma-separated list of roles that are allowed to delete assets. Default value: blank
xcelerate.grant.edit	Contains a comma-separated list of roles that are allowed to edit assets. Default value: blank
xcelerate.grant.inspect	Contains a comma-separated list of roles that are allowed to inspect assets. Default value: blank
xcelerate.grant.placepage	Contains a comma-separated list of roles that are allowed to place assets in the SitePlan tree. Default value: blank
xcelerate.grant.preview	Contains a comma-separated list of roles that are not allowed to preview assets with their templates. Default value: blank
xcelerate.grant.remove fromgroup	Contains a comma-separated list of roles that are allowed to remove assets from a workflow group. Default value: blank
xcelerate.grant.remove fromworkflow	Contains a comma-separated list of roles that are allowed to remove assets from workflow. Default value: blank
xcelerate.grant.rollback	Contains a comma-separated list of roles that are allowed to roll back assets to a previous version. Default value: blank
xcelerate.grant.set ExportData	Contains a comma-separated list of roles that are allowed to set export to disk (static publishing) starting point. Default value: blank
xcelerate.grant.set nestedworkflow	Contains a comma-separated list of roles that are allowed to set nested workflow. Default value: blank

Properties in futuretense_xcel.ini: **Authorization Tab** (continued)

Property	Description
xcelerate.grant.set participants	Contains a comma-separated list of roles that are allowed to set participants for workflow. Default value: blank
xcelerate.grant.set processdeadline	Contains a comma-separated list of roles that are allowed to set workflow process deadlines. Default value: blank
xcelerate.grant.set stepdeadline	Contains a comma-separated list of roles that are not allowed to set a deadline on a workflow step. Default value: blank
xcelerate.grant.share	Contains a comma-separated list of roles that are allowed to share assets with other sites (other than the site the asset was originally created in). Default value: blank
xcelerate.grant.show participants	Contains a comma-separated list of roles that are allowed to see the participants that are set for a workflow. Default value: blank
xcelerate.grant.show status	Contains a comma-separated list of roles that are allowed to see the status screen for assets. The status option shows up in the more ... drop-down box of the inspect window. The screen shows workflow, publishing, and revision tracking information about the asset that is being inspected. If the user belongs to one of the roles that is being granted the privilege, the option to view the status screen will show. Default value: blank
xcelerate.grant.show version	Contains a comma-separated list of roles that are allowed to see the list of versions for an asset. Note: The user can view the list of versions for an asset that is explicitly or implicitly checked out. The inspect form will display a Show Versions button if the user belongs to one of the roles that is granted the privilege. Default value: blank

futuretense_xcel.ini: Debug Tab

The **Debug** tab holds properties that enable the various WebCenter Sites debugging utilities. These properties are documented here in alphabetical order.

Properties in futuretense_xcel.ini: Debug Tab

Property	Description
am.debug	<p>Specifies whether AssetMaker logs debugging information about the asset types it makes. When this property is set to <code>on</code>, information about the creation of asset types is written to the WebCenter Sites log file.</p> <p>Default value: <code>off</code></p>
asset.debug	<p>Specifies whether Desktop and the Export Assets to XML publishing method log debugging information when they manipulate assets. When this property is set to <code>on</code>, information about the manipulation of assets is written to the WebCenter Sites log file.</p> <p>Default value: <code>off</code></p>

futuretense_xcel.ini: Directories Tab

The **Directories** tab holds properties that enable the various WebCenter Sites directories, such as utilities. These properties are documented here in alphabetical order.

Properties in futuretense_xcel.ini: **Directories Tab**

Property	Description
xcelerate.local languagedir	<p>Specifies the directory path of the Sites Desktop client installation.</p> <p>This value is set by the WebCenter Sites installation.</p> <p>Default value: C:/FutureTense/futuretense_cs/xcelerate/Client/ClientInstall/CSDesktop</p>
xcelerate.lockdir	<p>Specifies the directory path (including the final slash) to the directory where WebCenter Sites stores information about the locks that lock data during database operations. If this WebCenter Sites system is installed on a cluster, this directory must have write permissions for and be accessible to all cluster members.</p> <p>This value is set by the WebCenter Sites installation.</p> <p>Default value: c:/FutureTense/lock/</p>
xcelerate.objpubdir	<p>Specifies the path to a directory in cluster-shared file space (including the terminating slash character) in which objects that get published are stored temporarily.</p> <p>This value is set by the WebCenter Sites installation.</p> <p>Default value: C:/FutureTense/objpubdir/</p>
xcelerate.pubkeydir	<p>Specifies the directory where the publishing system writes information about the items that have been published to the various target systems.</p> <p>This value is set by the WebCenter Sites installation.</p> <p>Default value: c:/FutureTense/pubkeys/</p>
xcelerate.saveSearchdir	<p>Specifies the defdir (default storage directory) for the SaveSearch table. This table has a URL column that holds the saved searches on a development or management system.</p> <p>This value is set by the WebCenter Sites installation.</p> <p>Default value: c:/FutureTense/Storage/SaveSearch</p>

Properties in futuretense_xcel.ini: **Directories Tab** (continued)

Property	Description
<code>xcelerate.sePath</code>	<p>Specifies the directory where search indexes are stored when you are using a search engine on your WebCenter Sites system.</p> <p>If you change this value, be sure to specify a directory that exists. (This property does not create the directory for you.)</p> <p>Legal values:</p> <ul style="list-style-type: none"> Windows NT or Windows 2000: c:/FutureTense/sedb Solaris or AIX: /export/home/FutureTense/sedb
<code>xcelerate.tempobjectsdirectory</code>	<p>Specifies the defdir (default storage directory) for the TempObjects table, a WebCenter Sites table that stores information about objects that are uploaded or in the process of being created until they are either saved or canceled.</p> <p>This value is set by the WebCenter Sites installation.</p> <p>Default value: c:/FutureTense/tempobjectsdirectory/</p>
<code>xcelerate.thumbnaildir</code>	<p>Specifies the directory where the template asset will store thumbnail images associated with template variant thumbnails.</p> <p>This value is set by the WebCenter Sites installation.</p> <p>Default value: C:/FutureTense/thumbnaildir/</p>
<code>xcelerate.workflowdir</code>	<p>Specifies the name of the directory that holds files related to workflow processes.</p> <p>This value is set by the WebCenter Sites installation.</p> <p>Default value: C:/FutureTense/workflowdir</p> <p>If you change the value from the default, be sure that directory exists.</p>

futuretense_xcel.ini: Element Override Tab

The **Element Override** tab holds properties that you can use to help customize the user interface. These properties are documented here in alphabetical order:

Properties in futuretense_xcel.ini: **Element Override Tab**

Property	Description
xcelelem.manageuserpub	<p>Defines the element that WebCenter Sites uses to manage the roles that users fulfill on sites in WebCenter Sites.</p> <p>Default value: Openmarket/Xcelerate/Actions/Security/AccessUserPublication</p>
xcelelem.publishfactors	<p>The name of the element used to provide additional publishing control factors. May be empty.</p> <p>Default value: Openmarket/Xcelerate/Actions/Publish/OverrideFactor</p>
xcelelem.publishoptions	<p>This property allows customization of a portion of the common options area of the publishing form.</p> <p>It is used by the Action/Publish/PublishOptions element.</p> <p>If this is defined, it names an element to call which will lay out the publishing options section of all the publishing forms.</p> <p>Default value: empty</p>
xcelelem.setpubid	<p>Deprecated.</p> <p>Specifies the name of the element that sets the pubid session variable when visitors first come to your site via a dynamic URL. It is run once per visitor session.</p> <p>Default value: OpenMarket/Xcelerate/Actions/Publish/SetPubid</p>

futuretense_xcel.ini: Preference Tab

The **Preference** tab holds properties that you use to configure the search feature, the tree, and the character set used on your system.

These properties are documented here in alphabetical order.

Properties in futuretense_xcel.ini: **Preference Tab**

Property	Description
<code>xcelerate.charset</code>	<p>Specifies the character set that WebCenter Sites uses to communicate with the server.</p> <p>Default value: UTF-8</p> <p>Changing this property from the default value may limit the characters that are supported.</p>
<code>xcelerate.email notification</code>	<p>Deprecated.</p> <p>Specifies whether the WebCenter Sites workflow e-mail notification feature is enabled.</p> <p>When this property is set to <code>true</code>, the workflow system sends e-mail messages to users when assets are assigned to them through a workflow process.</p> <p>Default value: <code>false</code></p> <p>See also, the “Email” section in the <i>WebCenter Sites Administrator’s Guide</i>.</p>
<code>xcelerate.restrict SiteTree</code>	<p>Specifies whether users other than admin users can toggle the tree on in the WebCenter Sites interface when it is configured to be toggled off by default (that is, the <code>xcelerate.showSiteTree</code> property is set to <code>false</code>).</p> <p>Set to <code>true</code> to enable only users with the <code>xceladmin</code> ACL to be able to toggle the tree back on.</p> <p>Default value: <code>false</code></p> <p>For more information about this feature, see the <i>WebCenter Sites Administrator’s Guide</i>.</p>
<code>xcelerate.seLimit</code>	<p>Specifies the maximum number of query results that should be returned from any internally conducted search engine query.</p> <p>Default value: 10000</p>

Properties in futuretense_xcel.ini: **Preference Tab** (continued)

Property	Description
<code>xcelerate.showSiteTree</code>	<p>Specifies whether the tree is displayed by default when any user logs in to the WebCenter Sites interface.</p> <p>Set to <code>false</code> if you want the tree to be toggled off by default.</p> <p>Default value: <code>true</code></p> <p>For more information about this feature, see the <i>WebCenter Sites Administrator's Guide</i>.</p>
<code>xcelerate.treehierasset type</code>	<p>Enables hierarchical display mode for SiteEntry, CSElement, Template, and Recommendation assets.</p> <p>The value of this property is a comma-delimited list of asset types that should be displayed in a hierarchy.</p> <p>Asset types whose assets should not be displayed in a hierarchy should not be included in the list.</p> <p>The hierarchical structure is based on the “/” the in the asset name. Each “/” in the asset name represents one hierarchy level, e.g. “/AssetName” is the top level, “//AssetName” is the next level, and so on.</p> <p>Default value: <code>SiteEntry,CSElement,Template,Recommendation</code></p>
<code>xcelerate.treeMaxNodes</code>	<p>Specifies the number of items that are displayed under a node in the tree in the WebCenter Sites interface. When a node has more than this number of items, WebCenter Sites prompts the user to enter search criteria to reduce the number.</p> <p>Default value: <code>100</code></p> <p>For more information about this feature, see the <i>WebCenter Sites Administrator's Guide</i>.</p>
<code>xcelerate.treeType</code>	<p>Specifies the kind of tree that is used in the WebCenter Sites interface.</p> <p>Legal values: <code>OMTree</code> or a value that specifies a customized replacement tree</p> <p>Default value: <code>OMTree</code></p> <p>Do not change this property without first consulting Oracle support personnel.</p>

Properties in futuretense_xcel.ini: **Preference Tab** *(continued)*

Property	Description
xcelerate.usese	<p>Specifies whether WebCenter Sites should use an installed search engine.</p> <p>Legal values: true false</p> <p>Default value: false</p>

futuretense_xcel.ini: Publishing Tab

The **Publishing** tab holds the properties that provide information to the WebCenter Sites publishing system, which also uses the properties in the `futuretense.ini` file (Export/Mirror tab). For descriptions of the properties, see “[Export/Mirror Tab](#)” on page 74.

Properties in futuretense_xcel.ini: Publishing Tab

Property	Description
<code>xcelerate.batchhost</code>	<p>Specifies the host name and port number of the server on which the publish process will run.</p> <p>Only one batch host is supported in a clustered WebCenter Sites environment. This property must be set on each cluster member to point to the same dedicated host.</p> <p>Legal value: <hostName>:<portNumber></p>
<code>xcelerate.batchmode</code>	<p>Defines the batch publishing mode.</p> <p>Legal values:</p> <ul style="list-style-type: none"> • <code>single</code>— batch host is a dedicated IP address. • <code>multiple</code>— batch host is a cluster IP address. <p>Default value: <code>single</code></p>
<code>xcelerate.batchload sizeonpublish</code>	<p>Controls the batch size of assets loaded during a publishing event.</p> <p>Default value: <code>250</code></p>
<code>xcelerate.batchpass</code>	<p>Specifies the password for the batch user.</p> <p>Default value: <code>xceladmin</code></p> <p>Be sure to change this value after you create the batch user for this WebCenter Sites system. For information, see the <i>WebCenter Sites Administrator's Guide</i>.</p>
<code>xcelerate.batchsave sizeonpublish</code>	<p>Controls the batch size of assets saved during a publishing event.</p> <p>Default value: <code>250</code></p>

Properties in futuretense_xcel.ini: **Publishing Tab** (continued)

Property	Description
xcelerate.batchuser	<p>The WebCenter Sites publishing system runs as a background process and you must configure a batch user account for the publishing system to use. This property specifies the user name of the batch user.</p> <p>Default value: admin</p> <p>Be sure to change this value after you create the batch user for this WebCenter Sites system. For information, see the <i>WebCenter Sites Administrator's Guide</i>.</p>
xcelerate.blobref	<p>The name of the class that manages the publish references for blobs. The default is provided here for reference only: com.openmarket.xcelerate.publish.BlobRef.</p> <p>Do not change the value of this property.</p> <p>For information about published references, see the <i>WebCenter Sites Administrator's Guide</i>.</p>
xcelerate.bulkapprove chunk	<p>Specifies the number of assets to approve at the same time, in the same batch or "chunk," when someone uses the Approve Multiple Assets feature in the WebCenter Sites interface.</p> <p>The feature approves all the assets that are selected for approval in batches and the number of assets in each batch is set by this property.</p> <p>Default value: 500</p> <p>For information about the Approve Multiple Assets feature, see the <i>WebCenter Sites Administrator's Guide</i>.</p>

Properties in futuretense_xcel.ini: **Publishing Tab** (continued)

Property	Description
<code>xcelerate.donotregenerate</code>	<p>Specifies whether cached pages are regenerated after a publishing session.</p> <p>Legal values:</p> <ul style="list-style-type: none"> • blank, that is, no value—means that all the pages in the cache that were affected by the publish session are refreshed. • <code>unknowndeps</code>—means that cached pages that were generated from an element that used a <code>RENDER.UNKNOWNDEPS</code> tag are not refreshed. • * (asterisk)—means none of the pages in the cache are refreshed. In other words, the affected pages are refreshed only when a visitor requests the page. <p>Default value: blank</p> <p>Do not change the value of this property without first consulting Oracle support personnel.</p>
<code>xcelerate.exportmaxfilename</code>	<p>This is the maximum length of any file name generated during export publishing.</p> <p>If you are running Windows NTFS, you may want to set this to a low value to make it possible to re-export, delete or rename files created by the export-to-disk publish process. NTFS has an upper limit of 255 characters for any path name.</p>
<code>xcelerate.mirrorini</code>	<p>If you have had the element identified by the <code>xcelerate.remotecall</code> property modified in such a way that it needs information from additional property files other than <code>futuretense.ini</code>, this property specifies the names of all the property files that are needed.</p> <p>Default value: <code>futuretense.ini</code></p> <p>Do not modify this value to include additional property files without consulting Oracle support personnel.</p>
<code>xcelerate.pageref</code>	<p>Specifies the name of the class that manages publish references for pages. The default is provided here for reference only:</p> <p><code>com.openmarket.xcelerate.publish.PageRef.</code></p> <p>Do not change the value of this property.</p>

Properties in futuretense_xcel.ini: **Publishing Tab** (continued)

Property	Description
<code>xcelerate.presaveelt</code>	Specifies the name of the element called on the mirror target during publish after the assets' primary rows have been mirrored, but prior to the deserialization and <code>asset.save</code> of the flex and complex assets. Use <code>PresaveElement</code> for standard mirror publish.
<code>xcelerate.pubabortelt</code>	Specifies the name of the element called on the mirror target if the publish fails. Default value: <code>PubAbortElement</code> for standard mirror publish.
<code>xcelerate.pubcleanupelt</code>	Specifies the name of the element that the publishing system uses during the cleanup phase of a mirror publish operation. Default value: <code>PubCleanupElement</code> Do not modify this value without consulting Oracle support personnel.
<code>xcelerate.publishall assettypes</code>	Specifies whether to publish all asset types on mirror publish. Legal values: <code>true</code> <code>false</code> If set to <code>true</code> all asset types will be published. If not set to <code>true</code> , only asset types of the assets involved in the publish and their dependent asset types will be published. Note: If you want to set this property to <code>true</code> , you have to make sure that all asset types that exist on the source server also exist on the publish destination.
<code>xcelerate.publish invalidate</code>	Specifies whether an asset is marked as changed on the destination system when an asset is published. If it is marked as changed, it must be approved on that system before it can be published from that system to a new destination. Legal values: <code>true</code> <code>false</code> Default value: <code>true</code> Because having the publishing system take the time to mark the assets as changed on the destination adds time to the publishing session, typically you leave this property set to <code>true</code> on development and management systems but change it to <code>false</code> on delivery systems.

Properties in futuretense_xcel.ini: **Publishing Tab** (continued)

Property	Description
xcelerate.pubsetupelt	<p>Specifies the name of the element that the publishing system uses during the setup phase of a mirror publish.</p> <p>Default value: PubSetupElement</p> <p>Do not modify this value without consulting fatwire Professional Services or fatwire Customer Support.</p>
xcelerate.remotecall	<p>Specifies the pagename that is invoked on the target system during a mirror publishing session.</p> <p>Default value: Openmarket/Xcelerate/PrologActions/ Publish/Mirror1/RemoteCall</p> <p>Do not modify this element or change the value of this property without assistance from Oracle support personnel.</p>
xcelerate.templatdefault	<p>The name of the template to use if a template cannot be found to render an asset type.</p> <p>Default value: Openmarket/ TemplateDefault</p>

futuretense_xcel.ini: Transformer Tab

The **Transformer** tab holds the properties that apply to content created in Sites Desktop, where both text and a single image are saved to the same blob attribute, and format is preserved (i.e., both the text and the image are preserved when converted to an asset). The *WebCenter Sites Administrator's Guide* covers the remaining scenarios, such as a blob attribute holding data of a single type, for which setting a property is not required.

Properties in futuretense_xcel.ini: Transformer Tab

Property	Description
<code>transformer.imgdir</code>	<p>Specifies the path to the image files that Sites Desktop will use when transforming a Word document into an asset. This property applies only to assets created in Sites Desktop, where both text and a single image are saved to the same blob attribute, and format is preserved.</p> <p>Note: This property is not set by the installer. Leaving it blank will cause Sites Desktop to ignore the <code><transformer.imgdir></code> directory and therefore omit image files from the assets it creates from Word documents.</p> <p>When a blob attribute in a given asset type is enabled for Sites Desktop and it supports data of mixed types, users can save text and a single image to the blob attribute when they create or edit the Word document. When the Word document is saved, its content is transformed into an asset. During transformation, the image file is written to the <code><transformer.imgdir></code> directory, while the text is stored as HTML in the URL column in the WebCenter Sites database. The HTML file has an unmanaged link to the image in the <code><transformer.imgdir></code> directory. (The asset is accessible from the WebCenter Sites user interface; the Word document remains intact and available for editing through Sites Desktop.) Blob fields containing data of mixed types require you to implement a process that regularly mirrors the <code><transformer.imgdir></code> directory to the delivery system, because the publishing system does not mirror this directory.</p> <p>To set the <code><transformer.imgdir></code> path</p> <ol style="list-style-type: none"> 1. Define a webroot somewhere that points to a directory in a shared file system which is accessible from all cluster members. 2. Set <code>transformer.imgurl</code> to be either the relative URL path (starting with /) of the webroot you defined, or the absolute URL (starting with http) of the webroot. 3. Set <code>transformer.imgdir</code> to the directory path that the webroot points to. <p>For more information about the storage of content created (or edited) in Sites Desktop, see the <i>WebCenter Sites Administrator's Guide</i>.</p>

Properties in futuretense_xcel.ini: **Transformer Tab** (continued)

Property	Description
transformer.imgurl	<p>This property specifies either the relative URL path or the absolute path of the webroot that Sites Desktop will use to store the image files it extracts from Word documents when converting the Word documents to assets. (The Word documents remain intact.)</p> <p>Note: This property is used with the transformer.imgdir property and applies only to assets created in Sites Desktop, where both text and a single image are saved to the same blob attribute, and the format is preserved.</p> <p>This property is not set by the installer. Leaving it blank will cause Sites Desktop to ignore the directory containing the image files (<transformer.imgdir>) and therefore omit image files from the assets it creates from Word documents.</p> <p>For more information about the usage of this property, see transformer.imgdir.</p>

futuretense_xcel.ini: xcelerate Tab

The **xcelerate** tab holds the properties that specify such things as default administrative settings, whether Web Mode (in the Site Contributor interface) is enabled, whether workflow configuration and search engine are being used, and whether LDAP is being used. These properties are documented here in alphabetical order:

Properties in futuretense_xcel.ini: xcelerate Tab

Property	Description
<code>cs.binarypath</code>	Set at installation time. This property points to the location where WebCenter Sites and third-party binaries (shared objects) are stored. Note: Do not change the value of this property.
<code>wem.enabled</code>	This is a system property. Its value must not be changed except by the silent or GUI installer. Default value: <code>true</code> (given that the WEM Framework is installed by default.)
<code>xcelerate.adminacl</code>	Specifies the ACL that users must be assigned so they can access administrator functions (that is, any of the functions that appear on the Admin tab in the WebCenter Sites interface). Default value: <code>xceladmin</code> If you change the value of this property to a different ACL, be sure to assign that ACL to all the tables that currently have the <code>xceladmin</code> ACL assigned to them.
<code>xcelerate.adminrole</code>	Specifies an ACL that is set for all administrative tables during installation. Default value: <code>xceladmin</code> Do not change the value of this property after your system is installed.
<code>xcelerate.approval.dependency.chunksize</code>	This property defines the chunk size used in approval. (Chunk size is the number of assets that are processed by WebCenter Sites at a given time during approval to publish. Processing involves calculating dependencies.) Default value: <code>250</code> (for backward compatibility) Legal values: any integer between 1 and 1000 Recommended value: <code>1</code>

Properties in futuretense_xcel.ini: **xcelerate** Tab (continued)

Property	Description
xcelerate.base	<p>Specifies the top-level (base) directory of the WebCenter Sites elements. During installation, the installer might need to edit this value to indicate where the WebCenter Sites elements are in your installation.</p> <p>Default value:</p> <ul style="list-style-type: none"> Windows NT or Windows 2000: c:/Fatwire/elements/OpenMarket/Xcelerate Solaris or AIX: /export/home/Fatwire/elements/OpenMarket/Xcelerate <p>Do not change the value of this property after your system is installed.</p>
xcelerate.crosssiteassign	<p>Specifies whether users from more than one site can participate in the same workflow process.</p> <p>Legal values: true false</p> <p>Default value: false</p>
xcelerate.defaultlang	<p>Specifies the default language.</p> <p>Default value: en_US</p>
xcelerate.defaultpreview urlgenerator	<p>Set to the preview generator name to generate URLs for preview, if no site-specific one is described.</p>
xcelerate.domain	<p>Specifies the domain name of the system, not including the server (machine) name. This property is used by applications that have been integrated with WebCenter Sites and that have a browser interface.</p>
xcelerate.editrole	<p>Specifies an ACL that is set for editorial tables during installation.</p> <p>Default value: xceleditor</p> <p>Do not change the value of this property after your system is installed.</p>
xcelerate.enableinsite	<p>Enables or disables Web Mode (in the Sites Contributor interface) for this WebCenter Sites system. A value of true enables Web Mode.</p> <p>Default value: false</p> <p>Do not enable Web Mode on your WebCenter Sites delivery system.</p>
xcelerate.imageurl	<p>Specifies the webroot for all image URLs used by the applications.</p>

Properties in futuretense_xcel.ini: **xcelerate** Tab (continued)

Property	Description
xcelerate.previewhost	<p>One of two properties that enable the preview host feature, this property defines the protocol, server, and port for the preview host to use.</p> <p>For information about this feature, see “Maintaining Separate Browser Sessions for Preview” in the <i>WebCenter Sites Administrator’s Guide</i>.</p> <p>If you provide a value for this property, use the following syntax:</p> <p>http://<servername>:<port></p>
xcelerate.previewervlet	<p>One of two properties that enable the preview host feature, this property specifies which servlet the preview host should use.</p> <p>For information about this feature, see “Maintaining Separate Browser Sessions for Preview” in the <i>WebCenter Sites Administrator’s Guide</i>.</p> <p>Legal values: ContentServer or Satellite</p> <p>Default value: Satellite</p>
xcelerate.previewurlpage name	<p>Set to the name of page to generate URLs for preview.</p> <p>Do not change the value of this property.</p>
xcelerate.publishquery style	<p>Defines the query style to use when getting a list of assets approved for publishing.</p> <p>Legal values: subquery, join</p>
xcelerate.rolemanager class	<p>Specifies the name of the role manager class. By default, the value of this property is set to the WebCenter Sites role management system.</p> <p>Default value: com.openmarket.xcelerate.roles.RoleManager</p> <ul style="list-style-type: none"> • If you are using a Sun ONE embedded Identity Server, set this property to the following value, exactly: com.openmarket.xcelerate.roles.IdentityServerRoleManager • If you are using a WebLogic embedded LDAP, set this property to the following value, exactly: com.openmarket.xcelerate.roles.FlatLDAPRoleManager

Properties in futuretense_xcel.ini: **xcelerate** Tab (continued)

Property	Description
xcelerate.searchResult Cols	<p>Specifies which columns are displayed in the search results list in the WebCenter Sites Admin interface. (Custom columns cannot be added.)</p> <p>Default value: name,modified,locale,startDate,endDate,assetType</p> <p>Additional values: description,status</p> <p>Note: Column names are case sensitive. The column order specified in this property <i>does not</i> affect the actual column order in the search results list. The actual order (by column display name) is Name, Description, Type (here, Type denotes assetType), Locale, Status, Modified, Start Date, End Date.</p>
xcelerate.systemid	<p>Specifies the identifier for this WebCenter Sites system. It is used for generating unique identifiers for exported data.</p> <p>Select a value that is different from the IDs of all other known WebCenter Sites systems. Otherwise, ID conflicts will arise.</p> <p>Default value: CSSystem</p> <p>Legal values: any alphanumeric string of 1–255 characters</p>
xcelerate.transformpath	<p>Set at installation time. This property sets the path to the directory where Sites Desktop temporarily stores the Microsoft Word files that WebCenter Sites will transform into assets.</p> <p>Note: Do not change the value of this property.</p>
xcelerate.treetabmanager class	<p>The class that implements ITreeTabManager to provide tree tab descriptions for WebCenter Sites.</p> <p>Default value: com.openmarket.xcelerate.treetab.TreeTabManager</p> <p>The default is provided here for reference only. Do not change the value of this property.</p>

Properties in futuretense_xcel.ini: **xcelerate** Tab *(continued)*

Property	Description
<code>xcelerate.usermanager</code> class	<p>The class that implements IUserManager to provide user services for WebCenter Sites.</p> <p>Default value: <code>com.openmarket.xcelerate.user.UserManager</code></p> <ul style="list-style-type: none">• If you want to implement LDAP attribute-mapping for site and role names, set this property to the following value, exactly: <code>com.openmarket.xcelerate.user.LDAPSchemaUserManager</code>• If you are using a WebLogic or Sun ONE Application Server embedded LDAP, set this property to the following value, exactly: <code>com.openmarket.xcelerate.user.FlatLDAPSchemaUserManager</code>
<code>xcelerate.workflowengine</code> class	<p>The class that implements IWorkflowEngine to provide workflow services for WebCenter Sites. The default is provided here for reference only: <code>com.openmarket.xcelerate.workflow.WorkflowEngine</code></p> <p>Do not change the value of this property.</p>

futuretense_xcel.ini: User Management Tab

The **User Management** tab holds the properties that specify various user attribute names, which hold different information about the user, such as the list of roles that the user has for a publication, the screen name that the user uses, and the list of sites for which the user is enabled.

Properties in futuretense_xcel.ini: User Management Tab

Property	Description
<code>xcelerate.displayable nameattr</code>	Specifies the name of the user attribute describing the displayable name, if different from the login name.
<code>xcelerate.emailattr</code>	Specifies the name of the user attribute that is used to identify a user's e-mail address to your WebCenter Sites system. These attributes are kept in the <code>SystemUserAttr</code> table. Default value: mail
<code>xcelerate.localeattr</code>	Specifies the name of the user attribute that identifies the locale that a user specifies if you have more than one language pack installed on your WebCenter Sites system. Default value: <ul style="list-style-type: none"> Blank when one language is present. locale when more than one language is present.
<code>xcelerate.pubrolesattr</code>	Specifies the name of the user attribute that lists the roles that the user has for publication. This property is only used if <code>xcelerate.usermanagerclass</code> is set to <code>com.openmarket.xcelerate.user.LDAPAttrUserManager</code> This is combined with the publication id to obtain the attribute name containing the roles the user has for the publication. If value is not set, the <code>UserPublication</code> table is used, or some other LDAP User Manager Plug-in is used.

Properties in futuretense_xcel.ini: **User Management Tab** *(continued)*

Property	Description
<code>xcelerate.sitenameattr</code>	<p>Specifies the naming attribute of the site entries.</p> <p>This property is only used if <code>xcelerate.usermanagerclass</code> is set to <code>com.openmarket.xcelerate.user.LDAPSchemaUserManager</code>.</p> <p>By default, this value is blank, which means that information about a user's roles is stored in the <code>UserPublication</code> table, or some other LDAP User Manager plug-in is used.</p> <p>If there is a value specified for this property, the <code>xcelerate.usermanagerclass</code>, and <code>xcelerate.sitesroot</code> properties must also be configured correctly.</p>
<code>xcelerate.sitesattr</code>	<p>Specifies the name of the user attribute describing which publications the user has roles for.</p> <p>This property is used only if <code>xcelerate.usermanagerclass</code> is set to <code>com.openmarket.xcelerate.user.LDAPAttrUserManager</code>.</p> <p>If there is a value for this property, it is combined with the value of the <code>pubid</code> column and the value for the <code>xcelerate.pubroleattr</code> property to determine a user's access rights in the WebCenter Sites interface.</p> <p>By default, this value is blank, which means that information about a user's roles is stored in the <code>UserPublication</code> table, or some other LDAP User Manager plug-in is used.</p>
<code>xcelerate.sitesroot</code>	<p>Specifies the root node (dn) under which sites are located.</p> <p>This property is used only if <code>xcelerate.usermanagerclass</code> is set to <code>com.openmarket.xcelerate.user.LDAPSchemaUserManager</code>.</p> <p>By default, this value is blank, which means that information about a user's roles is stored in the <code>UserPublication</code> table, or some other LDAP User Manager plug-in is used.</p> <p>If there is a value specified for this property, the <code>xcelerate.usermanagerclass</code> and <code>xcelerate.sitenameattr</code> properties must also be configured correctly.</p>

Properties in futuretense_xcel.ini: **User Management Tab** *(continued)*

Property	Description
xcelerate.userimageattr	This property points to the <code>imagesrc</code> attribute in the WEM Framework user's account (accessible from the WEM Admin interface). The attribute contains image data in a base 64 encoded string. This property fetches the image.

futuretense_xcel.ini: User Defined Tab**Properties in futuretense_xcel.ini: User Defined Tab**

Property	Description
<code>xcelerate.ckeditor.basepath</code>	CKEditor basepath; that is, the location of the CKEditor files in the WebCenter Sites application. Default value: <code>/<URI>/ckeditor/</code>
<code>ckeditor.showIncludedElementInSpan</code>	Controls how CKEditor behaves when you include assets within text. When you include assets that use <code><div></code> tags, CKEditor does not change them to <code></code> tags. If you want CKEditor to change <code><div></code> tags to <code></code> tags, add this property and set it to <code>true</code> .
<code>xcelerate.imageeditor.basepath</code>	Online Image Editor (OIE) basepath; that is, the OIE archive location (relative URL), file name, and version. Default value: <code><URI>/ImageEditor/OIE.cab#version=3,0,1,10</code>
<code>xcelerate.imageeditor.clarkii.basepath</code>	Path to the Clarkii Online Image Editor files in the WebCenter Sites application. Default value: <code><application_context_root>/ImageEditor/clarkii/</code>
<code>xcelerate.useDimensionAssets</code>	This property is supported only on delivery systems. This property controls whether a WebCenter Sites delivery system queries the Dim and DimP database tables for Dimension assets. If you do not use Dimension assets (i.e., for multilingual support), do the following to prevent your delivery system from unnecessarily querying the Dim and DimP tables: <ol style="list-style-type: none">1. Add this property to <code>futuretense_xcel.ini</code> and set it to <code>false</code>.2. Set <code>-Dcs.disable.dimensions.in.ui</code> for the JVM to <code>true</code> in the application server startup script.

Properties in futuretense_xcel.ini: **User Defined Tab** (continued)

Property	Description
<code>advancedUI.enableAssetForms</code>	<p>Used to enable and disable the WebCenter Sites Admin interface for content contributors. Access to the following assets is affected:</p> <ul style="list-style-type: none">• All flex assets and their parent assets• All basic assets• Engage assets, such as recommendations, segments and promotions• Query, Collection, and Page assets <p>By default, this property is set to <code>false</code>, which disables the WebCenter Sites Admin interface for content contributors. The assets listed above cannot be created, edited, searched for, or deleted, except from the WebCenter Sites Contributor interface, where they are supported by default.</p> <p>Note: In the Contributor interface, asset types and assets intended for developers are either available only for inspection or they are inaccessible. They must be accessed from the WebCenter Sites Admin interface. For a comparison of features in the Contributor and Admin interfaces, see the <i>WebCenter Sites User's Guide</i>.</p> <p>Default value: <code>false</code></p>

gator.ini

Properties in `gator.ini` are organized by function on the following tabs in the Property Editor:

- [Gator Tab](#)
- [User Defined Tab](#)

gator.ini: Gator Tab

Properties in `gator.ini`: **Gator Tab**

Property	Description
<code>cc.attrDisplayStyle</code>	<p>The field to display (name or description) to describe attributes on a FlexAsset or FlexGroup ContentForm or ContentDetails screen.</p> <p>Possible values: name or description</p> <p>Default value: name</p>
<code>cc.attributeinheritance</code>	<p>A boolean that Gator uses to determine whether attributes should be inherited from parent to child.</p> <p>Default value: true</p>
<code>cc.extrapath</code>	<p>A boolean that Gator uses to determine if blobs should have extra path information prepended to avoid directory capacity issues on Unix.</p> <p>Default value: true</p>
<code>cc.fullconstraint</code>	<p>A boolean that Gator uses to determine if nested queries should include data from the outer query.</p> <p>Possible values: true false</p> <p>Default value: true</p>
<code>cc.money</code>	<p>The sql for defining a field that will contain monetary values. Choose the default or contact your database administrator.</p> <p>Default value: NUMERIC(20,3)</p> <p>Do not change this value without consulting your database administrator.</p>

Properties in gator.ini: **Gator Tab** (continued)

Property	Description
cc.querystyle	<p>A boolean that Gator uses to determine which basic form of assetset query to generate.</p> <p>Possible values: subquery, join, or intersect</p> <p>Default value: subquery</p> <p>Note that setting the value of this property to intersect functions only if your database can support intersection queries.</p>
cc.string	<p>The sql for defining a field that will contain string values.</p> <p>Default value: SEARCHVARCHAR</p> <p>Do not change this value without consulting your database administrator.</p>
cc.textdistinct	<p>A boolean describing whether your database can support DISTINCT on attributes of type TEXT.</p> <p>Default value: no</p>
cc.url	<p>The sql for defining a field that will contain URLs.</p> <p>Default value: VARCHAR(128)</p> <p>Do not change this value without consulting your database administrator.</p>
cc.urlattrpath	<p>Specifies the default base path Gator uses for URL attribute files.</p> <p>Default value: c:/futuretense/futuretense_cs/urlfiles</p>
cc.useLegacyInputNames	<p>Specifies the boolean that Gator uses to determine the input names of attributes on FlexAsset/Parent forms. Turn this property on if you need to support custom attribute editors that have not been updated to the new format.</p> <p>Default value: false</p>
mwb.assetsetclass	<p>Specifies the name of the class that supplies the services for assetset management.</p> <p>Default value: com.openmarket.gator.assetset.AssetSet</p> <p>Do not change the value of this property. The default is provided here for reference only.</p>

Properties in `gator.ini`: **Gator Tab** (continued)

Property	Description
<code>mwb.cartclass</code>	<p>The name of the class that supplies the services for cart management.</p> <p>Default value: <code>com.openmarket.catalog.cart.Cart</code></p> <p>Do not change the value of this property. The default is provided here for reference only.</p>
<code>mwb.cartsetclass</code>	<p>Specifies the name of the class that supplies the services for cart set management.</p> <p>Default value: <code>com.openmarket.catalog.cartset.CartSet</code></p> <p>Do not change the value of this property. The default is provided here for reference only.</p>
<code>mwb.commercecontextclass</code>	<p>Specifies the name of the class that supplies the services for commerce context.</p> <p>Default value: <code>com.openmarket.gator.commercecontext.CommerceContext</code></p> <p>Do not change the value of this property. The default is provided here for reference only.</p>
<code>mwb.commerceengineclass</code>	<p>Specifies the name of the class that supplies the services for commerce engine management.</p> <p>Default value: <code>com.openmarket.cscommerce.txcart.TransactEngine</code></p>
<code>mwb.commerceuserclass</code>	<p>Specifies the name of the class that supplies the services for commerce user management.</p> <p>Default value: <code>com.openmarket.catalog.cart.CommerceUser</code></p>
<code>mwb.conservativedependencies</code>	<p>Specifies the types of dependencies between:</p> <ul style="list-style-type: none"> flex assets and flex attributes flex assets and flex definitions <p>If you want dependencies to be <i>exact</i> between flex assets and flex attributes, and between flex assets and flex definitions, then set this property to <i>true</i>. For information about <i>exact</i> and <i>exists</i> dependencies, see the <i>WebCenter Sites Administrator's Guide</i>.</p> <p>Default value: <code>false</code></p>

Properties in `gator.ini`: **Gator Tab** (*continued*)

Property	Description
<code>mwb.defaultattributes</code>	Specifies the default attribute asset name for Gator to use when creating assetsets. Default value: blank
<code>mwb.externalattributes</code>	Specifies a boolean that Gator uses to determine if forms should allow users to define external attributes. Default value: true
<code>mwb.path</code>	Specifies the directory where Gator is installed. Be sure to end the directory with a forward slash (/). Default value: <code>c:/nas21/apps/</code> Do not change the value of this property.
<code>mwb.promotioncutoff</code>	Specifies the confidence rating that determines whether a visitor qualifies for a promotion. Possible values: integers between 0 and 100, inclusive Default value: 50 Do not change the value of this property.
<code>mwb.searchdir</code>	Specifies the directory where Gator places rich-text indexes. Be sure to end the directory with a forward slash (/). Default value: <code>c:/futuretense/gator/search/</code> Do not change the value of this property.
<code>mwb.searchstateclass</code>	Specifies the name of the class that supplies the services for search state management. Default value: <code>com.openmarket.gator.searchstate.SearchState</code> Do not change the value of this property. The default is provided here for reference only.

Properties in `gator.ini`: **Gator Tab** *(continued)*

Property	Description
<code>mwb.segmentcutoff</code>	<p>The confidence rating that determines whether to include a visitor in a segment.</p> <p>Possible values: integers between 0 and 100, inclusive.</p> <p>Default value: 50</p> <p>Do not change the value of this property.</p>

gator.ini: User Defined TabProperties in `gator.ini`: **User Defined Tab**

Property	Description
----------	-------------

Note: This tab, by default, has no properties.

log4j.properties

Apache log4j is used as the logging system in new WebCenter Sites 11gR1 installations.

Note

While Apache log4j is supported in the process of upgrading to WebCenter Sites 11gR1, installation engineers have the option to continue using Jakarta Commons Logging if the source system (FatWire Content Server 7.6 patch 1 or patch 2) was set to use Jakarta Commons Logging. Once a system is upgraded, switching to Apache log4j becomes a manual process, as described in “Setting Up Apache log4j” in the *Oracle WebCenter Sites Administrator’s Guide*.

When Apache log4j is set up, two files are configured:

- The `commons-logging.properties` file, in which the property `org.apache.commons.logging.Log` is set to specify the `Log4JLogger` (its value is the class name `com.fatwire.cs.core.logging.Log4JLogger`).
- The `log4j.properties` file is created to specify how information must be logged and which type of information will be logged. The `log4j.properties` file contains the following entries:
 - A set of appenders named `FWDefaultAppender`, which specify how information must be logged. For example, the property `FWDefaultAppender.File` specifies the WebCenter Sites log file and its location. The list of properties is available in “Configure log4j” in the *WebCenter Sites Administrator’s Guide*. For descriptions of these and other log4j-specific properties, see the Apache log4j documentation.
 - WebCenter Sites loggers, which determine the type of information that will be logged and at which severity level. The loggers are copied from the `commons-logging.properties` file (see [page 20](#)) to the `log4j.properties` file and their names are prefaced with `log4j.logger`.

For example, in the `commons-logging.properties` file, the following logger is used to specify the log severity for messages related to database access, queries, and statement execution:

```
logger.com.fatwire.logging.cs.db
```

When copied to the `log4j.properties` file, the logger is named as follows:

```
log4j.logger.com.fatwire.logging.cs.db
```

For descriptions of WebCenter Sites loggers, see `commons-logging.properties` on [page 20](#).

When log4j is set up, the WebCenter Sites Admin interface displays the **Configure log4j** tool in the **System Tools** node, on the **Admin** tab. The **Configure log4j** tool enables general administrators to view current loggers, temporarily change logger levels, and add new loggers directly from the administrator’s interface. Changes made from the Admin interface remain in effect only until WebCenter Sites is restarted. They will persist upon restart only if the text version of the logger properties is copied from the interface to the `log4j.properties` file. (Changes that are made directly in the `log4j.properties` file will not be applied to WebCenter Sites until the system is restarted.) For more information about the **Configure log4j** tool, see the *WebCenter Sites Administrator’s Guide*.

logging.ini (Deprecated)

The `logging.ini` file holds properties that configure the Logging module. The Logging module writes messages to the `futuretense.txt` file.

Note

The Logging module is deprecated. It is used only by the Directory Services API.

Properties in the `logging.ini` file are organized by function on the following tabs in the Property Editor:

- [Global Data Tab](#)
- [Message Resources Tab](#)
- [User Defined Tab](#)

logging.ini: Global Data Tab

The **Global Data** tab holds one property:

Properties in `logging.ini`: Global Data Tab

Property	Description
<code>log.filterLevel</code>	<p>Deprecated.</p> <p>The severity threshold that determines the amount of messages that the Logging module writes to the log.</p> <p>Possible values:</p> <ul style="list-style-type: none">• <code>info</code>: writes all informational, warning, error, severe, and fatal messages.• <code>warning</code>: excludes informational messages; writes warning, error, severe, and fatal messages.• <code>error</code>: excludes warning and informational messages; writes error, severe, and fatal messages.• <code>severe</code>: excludes error, warning, and informational messages; writes severe and fatal messages.• <code>fatal</code>: writes fatal messages only.

logging.ini: Message Resources Tab

The Message Resources tab holds properties that provide logical mappings for the message bundles that are located, delivered, and reported by the Logging Module when the module is invoked by various components of the applications.

Caution

Do **not** change the values of any properties on this tab.

Properties in logging.ini: Message Resources Tab

Property	Description
<code>log.Directory.messages</code>	Deprecated. Java resource bundle to use for the Directory Services API. Default value: <code>com.openmarket.directory.DirectoryResources</code> . Do not change the value of this property.
<code>log.Logger.messages</code>	Deprecated. Java resource bundle to use for the Logging module. Default value: <code>com.openmarket.logging.LoggerMessageResources</code> Do not change the value of this property
<code>log.transformer.messages</code>	Deprecated. Class that provides message resources for the Default Transformer WebMethodsEnterprise Connector Subsystem.
<code>log.wmentconnector.messages</code>	Deprecated. Class that provides message resources for the WebMethodsEnterprise Connector System.

logging.ini: User Defined Tab**Properties in logging.ini: User Defined Tab**

Property	Description
----------	-------------

Note: This tab, by default, holds no properties.

omii.ini

The `omii.ini` file is a system-specific file. It is created during the installation of WebCenter Sites to record the installation conditions and options that are chosen for WebCenter Sites.

Caution

The `omii.ini` file is used by the WebCenter Sites installer during re-installations and upgrades. Do **not** modify this file in any way.

omproduct.ini

The `omproduct.ini` file is a system-specific file. It is created during the installation of WebCenter Sites to record information about the Oracle products and sample site components that are chosen for installation with WebCenter Sites.

Caution

The `omproduct.ini` file is used by the WebCenter Sites installer during re-installations and upgrades. Do **not** modify this file in any way.

satellite.properties

The `satellite.properties` file is created on each WebCenter Sites system because each WebCenter Sites system runs a Satellite servlet. When the Satellite servlet is running in the same virtual machine as the ContentServer servlet, it is said to be “co-resident.” Otherwise, it is remote.

`satellite.properties` is on each server that hosts a Satellite Server application. The function of `satellite.properties` is to configure the Satellite servlet that it controls.

Properties in the `satellite.properties` file are organized by function on the following tabs in the Property Editor:

- [Caching Tab](#)
- [Configuration Tab](#)
- [Remote Host Tab](#)
- [Sessions Tab](#)
- [User Defined Tab](#)

satellite.properties: Caching Tab

The **Caching** tab holds the Satellite Server cache settings.

The `file_size` property can significantly influence performance. To optimize performance, try to maximize the amount of memory caching. However, be sure that you do not exceed the host's memory capacity.

If you have lots of memory or a relatively small web site, Oracle recommends caching everything to memory by setting a large value. However, in calculating whether your entire web site can fit in memory, remember that expired web pages stay in memory until explicitly removed or until the cache cleaning thread removes them. Be sure to consider this fact when you set the value of the `cache_check_interval` property.

Properties in `satellite.properties`: Caching Tab

Property	Description
<code>cache_check_interval</code>	Deprecated. Applies to only legacy page caching. This property controls the frequency of the cache cleaner thread. Expired objects are not pruned from cache when they expire. They are pruned either when they are requested and found invalid, or when a cache cleaner thread explicitly prunes them. In minutes, specify the pause between executions of the cache cleaner thread.
<code>cache_folder</code>	Applies to only legacy page caching. This property specifies the location of disk based cache data. If this property is left blank, cached data will be stored in the context's <code>temp</code> folder. Default value: blank
<code>cache_max</code>	Applies to only legacy page caching. This property specifies the maximum number of objects to maintain in the cache. Objects are removed from the cache if the size specified is exceeded; an LRU method is used to manage cache size limits.

Properties in `satellite.properties`: **Caching Tab** (continued)

Property	Description
<code>expiration</code>	<p>Applies to inCache page caching and legacy page caching. This property specifies expiration information (in the form of a <code>COM.FutureTense.Util.TimePattern</code> string) for all cached objects that do not have this information specified elsewhere.</p> <p>The expiration information for an object can be specified in the <code>cachecontrol</code> attribute on the <code>satellite.page</code> (and related) tags. For pages, expiration information can also be specified in the SiteCatalog's <code>sscachefinfo</code> column. For binary objects, the default value for the <code>cachecontrol</code> attribute is specified in the <code>futuretense.ini</code> file.</p> <p>Note that the outermost wrapper page of any request cannot specify an override, so this property is the only place where it can be controlled.</p> <p>Default value: <code>5:0:0 */*/*</code></p> <p>This means that everything in the Satellite Server cache expires every day at 5:00 a.m.</p> <p>The format is as follows:</p> <pre><hours>:<minutes>:<seconds> <daysOfWeek>/<daysOfMonth>/<months></pre> <p>Possible values:</p> <ul style="list-style-type: none"> • <code><hours></code>: 0 through 23, where 0 is midnight • <code><minutes></code>: 0 through 59 • <code><seconds></code>: 0 through 59 • <code><daysOfWeek></code>: 0 through 6, where 0 is Sunday • <code><daysOfMonth></code>: 1 through 31 • <code><months></code>: 1 through 12 <p>Other possible values:</p> <ul style="list-style-type: none"> • <code>never</code>, which means the page can expire only if the cache is full and it is the least recently used page • <code>immediate</code>, which means to never cache the page
<code>file_size</code>	<p>Applies to legacy page caching. This property specifies the size (in kilobytes) of objects that can be cached to disk. Smaller objects are retained in memory.</p> <p>This value should be adjusted for system RAM, disk speed, and so on.</p> <p>Default value: 250</p>

satellite.properties: Configuration Tab

The **Configuration** tab holds the properties that configure the Satellite servlet.

Properties in `satellite.properties`: **Configuration Tab**

Property	Description
<code>blocktimeout</code>	<p>Deprecated.</p> <p>Specifies the number of seconds a request will wait when another thread is in the process of requesting the same data from the host. Waiting helps reduce load on the host server when the cache is empty at the expense of individual user response time.</p> <p>Default value: 45</p> <p>A value of -1 means wait until the previous thread returns. A value of 0 means never wait.</p> <p>This value must be tuned based on the host performance, average request size, and network latency.</p> <p>It is safe to use a large number or -1.</p>
<code>password</code>	<p>Specifies the password that the Satellite engine will require for special functions like engine restart or cache reset.</p> <p>Be sure to change the username and password from the defaults.</p>
<code>readtimeout</code>	<p>Deprecated.</p> <p>Specifies the socket read timeout in seconds, after which a read terminates with an error. A value of 0 leaves the timeout to the Java runtime environment. A value of 3 sets a 3-second wait time.</p> <p>Default value: 45</p>
<code>transparent.content-type.pattern</code>	<p>A regular expression denoting content types that may contain nested components such as pagelets, links to other WebCenter Sites pages, or links to blobs. Pages whose content types match this pattern will be parsed by Satellite Server.</p>
<code>servlet</code>	<p>Specifies the URL pattern used to identify the Satellite Server servlet. Satellite Server will rewrite links and forms to use this URL pattern if pages are properly designed.</p> <p>Default value: <code>Satellite</code></p>

Properties in `satellite.properties`: **Configuration Tab** (*continued*)

Property	Description
<code>username</code>	<p>Specifies the username that the Satellite engine will require for special functions like engine restart or cache reset.</p> <p>Be sure to change the username and password from the defaults.</p>

satellite.properties: Remote Host Tab

The **Remote Host** tab holds properties that define the communications rules between Satellite Server and WebCenter Sites. These properties are documented here in alphabetical order:

Properties in `satellite.properties`: **Remote Host Tab**

Property	Description
<code>bservice</code>	<p>This value is the servlet path for the Blob Server servlet. It is used to tell Satellite Server where to go to resolve <code>satellite.blob</code> tags.</p> <p>Typical values include <code>/NASApp/cs/BlobServer</code> for iPlanet and <code>/servlet/BlobServer</code> for servlet runners.</p>
<code>host</code>	<p>The name of the remote host system running WebCenter Sites that the Satellite engine is caching requests for.</p> <p>This is required and there is no default.</p>
<code>port</code>	<p>The port number for communicating with the WebCenter Sites host.</p> <p>Default value: 80</p>
<code>protocol</code>	<p>The communication protocol between the Satellite Server host and the WebCenter Sites host. (Generally <code>http://</code> or <code>https://</code>).</p> <p>Note that setting the protocol to <code>https://</code> will not, in itself, ensure secure communications. You will still need to get a certificate.</p>
<code>service</code>	<p>This value is the servlet path for the WebCenter Sites servlet.</p> <p>It is used to tell Satellite Server where to go to resolve <code>satellite.page</code> tags.</p> <p>Typical values include <code>/NASApp/cs/ContentServer</code> for iPlanet and <code>/servlet/ContentServer</code> for servlet runners.</p>

satellite.properties: Sessions Tab

The **Sessions** tab holds properties that provide information about how the Satellite servlet should interpret a user's browser session.

Properties in `satellite.properties`: **Sessions Tab**

Property	Description
<code>contentserver.installation.folder</code>	<p>Replaces the <code>path.to.futuretense.ini</code> property.</p> <p>Applies to installations in which Satellite Server and WebCenter Sites are running in the same web application and must therefore share the user's session. This property specifies the path to the WebCenter Sites installation, enabling Satellite Server to access WebCenter Sites' resources, such as the system asset root and the <code>futuretense.ini</code> file.</p> <p>Possible values:</p> <ul style="list-style-type: none">• blank, if Satellite Server is running in a web application other than WebCenter Sites.• <code><cs_installation_dir></code> if Satellite Server is running in the same web application as WebCenter Sites. This directory contains the <code>futuretense.ini</code> file.
<code>cookieprefix</code>	<p>Satellite Server maintains a session between itself and the remote host on behalf of the client. Satellite Server needs to know the name of the session ID cookie the application server uses so that it can be properly tracked.</p> <p>Enter the possible session cookie name prefixes here, separated by a semicolon. If left blank, a default set will be used.</p>
<code>path.to.futuretense.ini</code>	<p>Replaced with: <code>contentserver.installation.folder</code></p>

Properties in `satellite.properties`: **Sessions Tab** (*continued*)

Property	Description
<code>sessionid.cookie.prefix</code>	<p>Users can now specify the prefix that is prepended to the session id cookie.</p> <p>The session id cookie is the session id cookie for the host (i.e., WebCenter Sites). Satellite Server needs to pass the session id cookie to the client in order to maintain a session between WebCenter Sites and the client.</p> <p>The cookie must be renamed, so it does not conflict with the session cookie that Satellite Server itself uses. The configurable prefix allows users who know the name of the session id cookie to construct the full cookie name. This can be used in a servlet filter or other mechanism to support custom functionality.</p>
<code>sharesession</code>	<p>Specifies whether the ContentServer servlet and the Satellite servlet share the user session.</p> <p>If Satellite Server is running remotely, set this to <code>false</code>; if Satellite Server and ContentServer are co-resident, set this property to <code>true</code>.</p> <p>If this property is not set appropriately, user-specific information may be inconsistent between pages.</p>

satellite.properties: Compatibility TabProperties in `satellite.properties`: **Compatibility Tab**

Property	Description
<code>formation</code>	<p>The Satellite servlet converts WebCenter Sites URLs that you GET or POST to into Satellite URLs. This property specifies which string to replace in the WebCenter Sites URL to create a Satellite URL.</p> <p>This value is case sensitive.</p> <p>Effective in Satellite Server 6, use the new <code>satellite.form</code> tag for all forms.</p>
<code>newformation</code>	<p>Specifies the replacement string in URLs to be GET'ed or POST'ed to the locally mapped servlet.</p> <p>This value is case sensitive.</p> <p>Effective in Satellite Server 6, use the new <code>satellite.form</code> tag for all forms.</p>
<code>globally_replace_content_server</code>	<p>If this property is set to <code>true</code>, Satellite Server will parse through all processable pages returned from WebCenter Sites and replace all instances of the string described by the <code>formation</code> property with the string described by the <code>newformation</code> property. It will also replace any occurrence of <code>ContentServer</code> with the string described by the <code>servlet</code> property.</p> <p>Effective in Satellite Server 6, use <code>satellite.link</code> or <code>RENDER.GETPAGEURL</code> for links and <code>satellite.form</code> for forms. If this is not possible, set this property to <code>true</code>.</p> <p>Default value: <code>false</code></p>

satellite.properties: User Defined TabProperties in `satellite.properties`: **User Defined Tab**

Property	Description
<code>appserverlink</code>	Deprecated. Value: 45
<code>servlet-path</code>	Deprecated. Value: /spark/
<code>propagatecache</code>	Used to enable the propagation of pages among nodes that are enabled for inCache page caching. Information about inCache can be found in the <i>WebCenter Sites Developer's Guide</i> .
<code>scratch.cleanup.schedule</code>	<p>Specifies the frequency, in minutes, of the event that runs to clean up files in the <code>Scratch</code> folder generated by Satellite Server caching. The frequency should be determined from the volume of pages loaded into cache and the <code>file_size</code> property (in the <code>satellite.properties</code> file).</p> <p>The default location of the <code>Scratch</code> folder depends on the application server. The path can be configured by setting the <code>cache_folder</code> property (in the <code>satellite.properties</code> file).</p> <p>Default value: 2</p>

ServletRequest.properties

The `ServletRequest.properties` file holds properties that specify configurations for certain types of requests (for example, a portal request or a Satellite Server request).

Properties in the `ServletRequest.properties` file are organized by function on the following tabs in the Property Editor:

- [Request Encoding Tab](#)
- [Request Threshold Tab](#)
- [URI Assembler Tab](#)
- [User Defined Tab](#)

ServletRequest.properties: Request Encoding TabProperties in ServletRequest.properties: **Request Encoding Tab**

Property	Description
<code>cs.charset</code>	The name of the optional parameter that defines the character encoding of the input.
<code>cs.contenttype</code>	<p>The default content type string used when streaming text. For example:</p> <p>For UTF-8: <code>text/html; charset=UTF-8</code> for UTF-8</p> <p>For Latin1: <code>text/html; charset=iso-8859-1</code></p> <p>Default value: <code>text/html</code></p>
<code>cs.contenttype.UTF-8</code>	<p>The preferred content type string used when decoding incoming http parameters. This property is designed for use with Japanese language installations, where the user intends to override <code>shift_jis</code> with a special encoding.</p> <p>For example: In Japanese environments with encoding such as <code>Cp943C</code>, set the value to: <code>cs.contenttype.shift_jis=Cp943C</code></p> <p>Default value: set by <code>cs.contenttype</code></p>

ServletRequest.properties: Request Threshold TabProperties in ServletRequest.properties: **Request Threshold Tab**

Property	Description
<code>cs.disksize</code>	Defines the maximum size of a binary blob in a page request that will be held in memory. Anything exceeding this size will be saved in a temporary file until it is needed.

ServletRequest.properties: URI Assembler TabProperties in ServletRequest.properties: **Request Encoding Tab**

Property	Description
path.BlobServer	The servlet context path for the Blob Server servlet. Typical values: /cs/BlobServer /servlet/BlobServer
path.CacheServer	The servlet context path for the Cache Server servlet. Typical values: /cs/CacheServer /servlet/CacheServer
path.CatalogManager	The servlet context path for the Catalog Manager servlet. Typical values: /cs/CatalogManager /servlet/CatalogManager
path.ContentServer	The servlet context path for the ContentServer servlet. Typical values: /cs/ContentServer /servlet/ContentServer
path.CookieServer	The servlet context path for the Cookie Server servlet. Typical values: /cs/CookieServer /servlet/CookieServer
path.DispatchManager	The servlet context path for the Dispatch Manager servlet. Typical values: /cs/DispatchManager /servlet/DispatchManager
path.PageDispatchServer	The servlet context path for the Page Dispatch Server servlet. Typical values: /cs/PageDispatchServer /servlet/PageDispatchServer

Properties in `ServletRequest.properties`: **Request Encoding** Tab (continued)

Property	Description
<code>path.SatelliteServer</code>	<p>The servlet context path for the Satellite Server servlet on the host that will be most often accessed. Forced Satellite Server URIs will use this path as the servlet context path.</p> <p>Typical values:</p> <ul style="list-style-type: none"> <code>/cs/Satellite</code> <code>/servlet/Satellite</code>
<code>path.SeedDispatchServer</code>	<p>The servlet context path for the Seed Dispatch Server servlet.</p> <p>Typical values:</p> <ul style="list-style-type: none"> <code>/cs/SeedDispatchServer</code> <code>/servlet/SeedDispatchServer</code>
<code>path.SyncSeedDispatchServer</code>	<p>The servlet context path for the Sync Seed Dispatch Server servlet.</p> <p>Typical values:</p> <ul style="list-style-type: none"> <code>/cs/SyncSeedDispatchServer</code> <code>/servlet/SyncSeedDispatchServer</code>
<code>path.TreeManager</code>	<p>The servlet context path for the Tree Manager servlet.</p> <p>Typical values:</p> <ul style="list-style-type: none"> <code>/cs/TreeManager</code> <code>/servlet/TreeManager</code>
<code>uri.assembler.1.classname</code>	<p>Specifies the classname for the default URI assembler to be used by this instance of WebCenter Sites. Users may override this value and specify a different assembler that conforms to the <code>com.fatwire.cs.core.uri.Assembler</code> interface.</p> <p>If the assembler specified by this class is unable to decode a URI, then WebCenter Sites will attempt to use the next ranked assembler to decode the URI. This process will continue until the URI is decoded.</p>
<code>uri.assembler.1.shortform</code>	<p>Specifies the short form name for the corresponding URI assembler. The short form is the name passed into <code>getURI</code> methods to identify which assembler to use; it is a nickname for the assembler.</p>

Properties in ServletRequest.properties: **Request Encoding Tab** (continued)

Property	Description
<code>uri.assembler.2.classname</code>	<p>Specifies the classname for the second URI assembler to be used by this instance of WebCenter Sites. Users may override this value and specify a different assembler that conforms to the <code>com.fatwire.cs.core.uri.Assembler</code> interface.</p> <p>If the assembler specified by this class is unable to decode a URI, then WebCenter Sites will attempt to use the next ranked assembler to decode the URI. This process will continue until the URI is decoded.</p>
<code>uri.assembler.2.shortform</code>	<p>Specifies the short form name for the corresponding URI assembler. The short form is the name passed into <code>getURI</code> methods to identify which assembler to use; it is a nickname for the assembler.</p>
<code>uri.assembler.3.classname</code>	<p>Specifies the classname for the third URI assembler to be used by this instance of WebCenter Sites. Users may override this value and specify another assembler that conforms to the <code>com.fatwire.cs.core.uri.Assembler</code> interface.</p> <p>If the assembler specified by this class is unable to decode a URI, then WebCenter Sites will attempt to use the next ranked assembler to decode the URI. This process will continue until the URI is decoded.</p>
<code>uri.assembler.3.shortform</code>	<p>Specifies the short form name for the corresponding URI assembler. The short form is the name passed into <code>getURI</code> methods to identify which assembler to use; it is a nickname for the assembler.</p>

ServletRequest.properties: User Defined TabProperties in ServletRequest.properties: **User Defined Tab**

Property	Description
----------	-------------

Note: This tab, by default, has no properties.

visitor.ini

The `visitor.ini` file is installed by WebCenter Sites. However, the properties in the file configure WebCenter Sites: Engage rather than WebCenter Sites. The properties configure the visitor data collection and other features provided by WebCenter Sites: Engage.

Properties in the `visitor.ini` file are organized by function on the following tabs in the Property Editor:

- [Visitor Data Tab](#)
- [User Defined Tab](#)

visitor.ini: Visitor Data Tab

The **Visitor Data** tab holds the main properties in the file.

Properties in `visitor.ini`: **Visitor Data** Tab

Property	Description
<code>vis.adminrole</code>	<p>Specifies the ACL that Engage users need in order to work with the visitor attribute, history attribute, history type, and recommendation asset types.</p> <p>Default value: <code>VisitorAdmin</code></p> <p>Do not change the value of this property.</p>
<code>vis.compileclasspath</code>	<p>Specifies the classpath against which to compile the rules.</p> <p>This value is set during the installation and should not be changed after that point.</p>
<code>vis.editrole</code>	<p>Specifies the ACL that two kinds of Engage users need:</p> <ul style="list-style-type: none"> • Content providers who use the WebCenter Sites system to create segments and promotions. • The visitors to your online site when you are using Engage to gather information about them for segments. <p>Default value: <code>Visitor</code></p> <p>Do not change the value of this property.</p>
<code>vis.genclasspath</code>	<p>Specifies the directory (including the final slash character) where rules-engine-generated class files for visitor data are stored.</p> <p>This value is set during the installation and should not be changed after that point.</p>

Properties in `visitor.ini`: **Visitor Data Tab** (continued)

Property	Description
<code>vis.money</code>	Specifies the SQL string for defining fields that hold monetary values. Do not change the value of this property without consulting your database administrator.
<code>vis.path</code>	Specifies the directory that holds the <code>ruleset.dtd</code> file, which is usually the installation directory. This value is set during installation. Do not change the value of this property.
<code>vis.rulesetxmlpath</code>	Specifies the <code>defdir</code> (default storage directory) for the XML versions of the rule sets. This value is set during installation. Do not change the value of this property.
<code>vis.sessiondata</code>	Specifies the <code>defdir</code> (default storage directory) for storing visitor session data. This value is set during installation. Do not change the value of this property.
<code>vis.update</code>	Specifies whether every page access will update the visitor timestamp in the visitor data. Possible values: <code>true</code> <code>false</code> Set to <code>true</code> if you want every page access to update the visitor timestamp in the visitor data; <code>false</code> otherwise. Default value: <code>true</code>
<code>vis.url</code>	Specifies the SQL string for defining visitor and history attributes of type URL. Default value: <code>VARCHAR(128)</code> Do not change the value of this property without consulting your database administrator.
<code>vis.urlpath</code>	Specifies the <code>defdir</code> for binary visitor and history attributes. Default value: <code>/futuretense/visurl/</code>

Properties in `visitor.ini`: **Visitor Data Tab** (*continued*)

Property	Description
<code>vis.useSessionVisitorConnection</code>	<p>This property determines whether Engage visitors will be tracked via the database- or memory-centric method, which improves the performance of heavily trafficked sites featuring Engage assets. In memory-centric tracking, WebCenter Sites stores visitor scalar attribute values to the add-on repository, and visitor history attribute values to its own database. All computations to determine a visitor's segments are performed in memory; results are cached.</p> <p>By default, this property is not automatically included in <code>visitor.ini</code>, in which case its value is understood to be <code>false</code> (i.e., database-centric).</p> <p>This property must be set on the delivery system in one of the following ways:</p> <ul style="list-style-type: none"> • If you wish to enable the database-centric method, set this property to <code>false</code>, leave it blank, or omit it from the file. • If you wish to enable the memory-centric method, set this property to <code>true</code> and ensure that supporting template code exists on the delivery system (in its absence, Engage visitors will be incorrectly tracked). For information about required code, see "Memory-Centric Visitor Tracking" in the Engage section of the <i>WebCenter Sites Developer's Guide</i>. <p>On content management systems, this property must be either set to <code>false</code> or omitted, given that visitor attributes are created and managed only on CM systems that are enabled for database-centric tracking. Management of visitor attributes is not supported on delivery systems; the attributes must be published to the delivery systems.</p>

visitor.ini: User Defined TabProperties in `visitor.ini`: **User Defined Tab**

Property	Description
----------	-------------

Note: This tab, by default, has no properties.

Part 2

Oracle WebCenter Sites Applications

This part lists the property files that are used by WebCenter Sites: Engage, WebCenter Sites: Analytics, and WebCenter Sites: Satellite Server.

This part contains the following sections:

- [Oracle WebCenter Sites: Analytics Properties](#)
- [Oracle WebCenter Sites: Engage Properties](#)
- [Oracle WebCenter Sites: Satellite Server Property Files](#)

Oracle WebCenter Sites: Analytics Properties

Oracle WebCenter Sites: Analytics requires that several properties in the `futuretense_xcel.ini` property file be set after Analytics is installed. These properties are described in [“Analytics Tab”](#) on page 100.

Oracle WebCenter Sites: Engage Properties

WebCenter Sites: Engage installs one property file, named `ms.ini`, which holds only the `ms.enable` property.

`ms.ini`

Properties in `ms.ini`

Property	Description
<code>ms.enable</code>	Set to <code>true</code> by the WebCenter Sites installation process, when Engage is installed and enabled.

Note

Engage configuration properties are located in the WebCenter Sites property file named `visitor.ini` ([page 158](#)).

Oracle WebCenter Sites: Satellite Server Property Files

When you install Satellite Server as a stand-alone application on a remote server, the `satellite.properties` is present on that server. For information about properties in the file, see [“satellite.properties”](#) on page 143.

Part 3

Third-Party Libraries and Applications

This part contains information about third-party libraries, as well as applications, and how Oracle WebCenter Sites integrates with them.

This part contains the following section:

- [HTTP Client Access](#)

HTTP Client Access

This section describes the Apache Commons HttpClient library and how WebCenter Sites integrates with this library.

Apache Commons HttpClient

WebCenter Sites uses Apache Commons HttpClient as the underlying library for all HTTP access. As of version 3, HttpClient supports the parameters that are posted at:

<http://jakarta.apache.org/commons/httpclient/preference-api.html>

The parameters function as follows:

- HttpClient parameters change the runtime behavior of HttpClient components. For example, if you want the `Post` operation to have a timeout that differs from the default, you can call `PostMethod.getParams().setParam("timeout", 1000)` before executing it.
- HttpClient parameters can be hierarchically linked. In top-down order, the levels of the hierarchy are: global, client, host, and method. Values that are set for parameters at higher levels are overridden by the values of equivalent parameters at lower levels.

Despite its flexibility, HttpClient has a limitation; that is—parameters can be set only programmatically. No configuration file can be written where parameter values can be specified by users or automatically retrieved by the library. The WebCenter Sites integration, however, overcomes this limitation as explained in the next section “[Integration with WebCenter Sites](#).”

Note

WebCenter Sites uses the parameters that are posted at <http://jakarta.apache.org/commons/httpclient/preference-api.html>. The parameters are listed in the table “[HttpClient Parameters](#),” on [page 169](#), along with descriptions (duplicated from the site named above). Changes to parameters and their functionality as defined by HttpClient are not automatically supported.

Integration with WebCenter Sites

WebCenter Sites abstracts HttpClient functionality by allowing WebCenter Sites users to create user-configurable property files. After creating the files, users populate them with the required HttpClient parameters (that is, parameters whose values differ from the default values), and place the property files into the classpath. WebCenter Sites loads the property files from the classpath and parses the parameters according to a predefined syntax (shown in the table “[HttpClient Parameters](#),” on [page 169](#)). The `HttpAccess` API retrieves the parameters and applies them at runtime.

WebCenter Sites supports a parameter hierarchy whose levels correspond directly to the levels that are defined in the `HttpAccess` Java API (provided in *WebCenter Sites Java Docs*). For each level, one or more property files can be created, depending on the

implementation, and populated with *any combination* of HttpClient parameters. The levels and property file naming conventions are given below:

Note

The property files must be created as text files, outside WebCenter Sites' Property Editor. Property file names are case sensitive and must be in lower case throughout.

- **HttpAccess (level 1)**

Property File: `httpaccess.properties`

The user specifies parameters and their values in the `httpaccess.properties` file. This file is applied to all HttpAccess instances that are created.

Overrides: Parameter values at the HttpAccess level are overridden by the values of equivalent parameters at levels 2, 3, and 4 (described below).

- **HostConfig (level 2)**

Property File: `<protocol>-<hostname>-<port number>.properties`

The user specifies host-specific parameters in each property file. For example, for a host named `targetserver` accessible at port 7001, the property file would be named `http-targetserver-7001.properties` and would contain HttpClient parameters specific to that host.

Overrides: Parameter values at the HostConfig level override the values of equivalent parameters at the HttpAccess level.

- **Request (level 3)**

Property File: `<request type>.properties`
where `<request type>` takes one of the following values: `post`, `get`, or `login`.

The user specifies parameters specific to a Request. For example, `post.properties` specifies HttpClient parameters applicable to instances of `post`.

Overrides: Parameter values at the Request level override the values of equivalent parameters at the HttpAccess and HostConfig levels.

- **Per host, per Request (level 4)**

Property File: `<request type>-<protocol>-<host name>-<port number>.properties`
where `<request type>` takes one of the following values: `post`, `get`, or `login`.

Parameters in this property file function as Request level parameters. However, they apply to a specific host.

Overrides: Parameter values specified at the “Per host, per Request” level override the values of equivalent parameters at the `HttpAccess`, `HostConfig`, and `Request` levels *for that particular host*.

The following example illustrates how an override takes effect from the “Per Host, Per Request” level. In this example, a user defines a property file named `login-http-m2-7002.properties`, where she specifies an `http.connection.timeout` of 100 seconds. The timeout applies strictly to the host machine named `m2` and port 7002. The timeout value overrides all timeout values that might be specified for `m2` at higher levels. For all other host machines, the timeout values remain unaffected.

WebCenter Sites supports all parameters defined by `HttpClient` in an externally configurable way. Furthermore, WebCenter Sites extends `HttpClient` functionality by enabling users to configure parameters externally and facilitating the specification of parameters at the fourth level (per host, per request).

In addition to all the parameters supported by `HttpClient`, WebCenter Sites' `HttpAccess` API defines a configuration property `cs.SecureProtocolSocketFactory` in `httpaccess.properties`. This property specifies the protocol socket factory to be used for SSL (Secure Socket Layer) connections. Three implementations are available at <http://jakarta.apache.org/commons/httpclient/sslguide.html>. Note that if you want to use SSL to connect to a host using self-signed certificates, you must configure the following:

```
cs.SecureProtocolSocketFactory=org.apache.commons.httpclient.  
contrib.ssl.EasySSLProtocolSocketFactory
```

WebCenter Sites does not provide this `EasySSLProtocolSocketFactory` class. You can obtain this class at <http://jakarta.apache.org/commons/httpclient/sslguide.html>. Make sure to build it differently for Sun and IBM JDKs, as the Apache implementation (at the link directly above) is Sun-specific. Alternatively you can write your own Socket factory implementation based on `HttpClient` documentation.

Note that there are two levels—connection manager and connection—in the `HttpClient` hierarchy for which parameters cannot be explicitly set, as the `HttpAccess` API does not directly support them. However, this does not mean users cannot configure those parameters; the parameters can be specified at a lower or higher corresponding level in the `HttpAccess` API.

Implementation

How does the WebCenter Sites user configure WebCenter Sites for http access? The user simply creates property files with appropriate names and places them in the classpath. The infrastructure will retrieve and use them. This seems like a good deal of work, especially given the number of parameters. However, by default, no properties or property files need to be created. All defaults will be used, and `HttpClient` takes the “best guess” values, which are usually the best settings for the given system. In 95% of the cases, “best guess” values are sufficient and users need not create any property files.

In the rare cases when one needs parameter values other than defaults, the WebCenter Sites infrastructure makes it possible to implement them by allowing the user to specify configuration in property files. This gives the user the full range of configuration capabilities that `HttpClient` itself is built upon.

HttpClient Parameters and WebCenter Sites Properties

The table in this section describes parameters that are supported by Apache Commons HttpClient. Descriptions in the table are duplicated from the following site:

<http://jakarta.apache.org/commons/httpclient/preference-api.html>

Syntax and default values are defined by Oracle, as they are specific to WebCenter Sites. Where syntax is straightforward, the “Syntax” field in the table below is left blank.

Note that changes to the parameters and their functionality are not automatically supported. Information in the table below is valid until Oracle issues an update.

In addition to supporting HttpClient parameters, WebCenter Sites defines the following property:

Property: `cs.SecureProtocolSocketFactory`

Usage: applicable only to the `httpaccess.properties` file

Description: defines the class used opening SSL Socket connections

Default: empty. The system will use the JSSE-based default implementation of HttpClient. Details are available at: <http://jakarta.apache.org/commons/httpclient/sslguide.html>

HttpClient Parameters

Name	Description
<code>http.authentication.preemptive</code>	<p>Defines whether authentication should be attempted preemptively.</p> <p>Type: Boolean</p> <p>Default value: <undefined></p>
<code>http.connection.stalecheck</code>	<p>Determines whether stale connection check is to be used. Disabling stale connection check may result in slight performance improvement at the risk of getting an I/O error when executing a request over a connection that has been closed at the server side.</p> <p>Type: Boolean</p> <p>Default value: <undefined></p>
<code>http.connection.timeout</code>	<p>The timeout until a connection is established. A value of zero means the timeout is not used.</p> <p>Type: Integer</p> <p>Default value: <undefined></p>

HttpClient Parameters *(continued)*

Name	Description
<code>http.connection-manager.class</code>	<p>The default HTTP connection manager class.</p> <p>Type: Class</p> <p>Syntax: Fully qualified classname</p> <p>Default value: SimpleHttpClientConnectionManager class</p>
<code>http.connection-manager.max-per-host</code>	<p>Defines the maximum number of connections allowed per host configuration. These values only apply to the number of connections from a particular instance of HttpClientConnectionManager. This parameter expects a value of type Map. The value should map instances of HostConfiguration to Integer s. The default value can be specified using ANY_HOST_CONFIGURATION.</p> <p>Type: Map</p> <p>Syntax: Specify \${<host>;<port>;<protocol>;<max connections>}</p> <p>Default value: <undefined></p>
<code>http.connection-manager.max-total</code>	<p>Defines the maximum number of connections allowed overall. This value only applies to the number of connections from a particular instance of HttpClientConnectionManager.</p> <p>Type: Integer</p> <p>Default value: <undefined></p>
<code>http.connection-manager.timeout</code>	<p>The timeout in milliseconds used when retrieving an HTTP connection from the HTTP connection manager.</p> <p>Type: Long</p> <p>Default value: <undefined></p>

HttpClient Parameters (continued)

Name	Description
http.dateparser.patterns	<p>Date patterns used for parsing. The patterns are stored in a Collection and must be compatible with SimpleDateFormat.</p> <p>Type: Collection</p> <p>Syntax: Specify the collection with each element enclosed in <code>\${<element>}</code>. e.g., <code>\${EEE, dd-MMM-yyyy HH-mm-ss z}\${EEE, dd MMM yy HH:mm:ss z}</code></p> <p>Default value: EEE, dd MMM yyyy HH:mm:ss zzz EEEE, dd-MMM-yy HH:mm:ss zzz EEE MMM d HH:mm:ss yyyy EEE, dd-MMM-yyyy HH:mm:ss z EEE, dd-MMM-yyyy HH-mm-ss z EEE, dd MMM yy HH:mm:ss z EEE dd-MMM-yyyy H:mm:ss z EEE dd MMM yyyy HH:mm:ss z EEE dd-MMM-yyyy HH-mm-ss z EEE dd-MMM-yy HH:mm:ss z EEE dd MMM yy HH:mm:ss z EEE,dd-MMM-yy HH:mm:ss z EEE,dd-MMM-yyyy HH:mm:ss z EEE, dd-MM-yyyy HH:mm:ss z</p>
http.default-headers	<p>The request headers to be sent per default with each request. This parameter expects a value of type Collection. The collection is expected to contain HTTP headers.</p> <p>Type: Collection</p> <p>Syntax: Specify each header in <code>\${name=<header name>; value=<header value>}</code></p> <p>Default value: <undefined></p>
http.method.multipart.boundary	<p>The multipart boundary string to use in conjunction with the MultipartRequestEntity. When this property is not set, a random value will be generated for each request.</p> <p>Type: String</p> <p>Syntax:</p> <p>Default value: <undefined></p>

HttpClient Parameters (*continued*)

Name	Description
<code>http.method.response.buffer.warnlimit</code>	<p>The maximum buffered response size (in bytes) that triggers no warning. Buffered responses exceeding this size will trigger a warning in the log. If not set, the limit is 1 MB.</p> <p>Type: Integer</p> <p>Default value: 1</p>
<code>http.method.retry-handler</code>	<p>The method retry handler used for retrying failed methods. For details see the Exception handling guide.</p> <p>Type: <code>HttpMethodRetryHandler</code></p> <p>Syntax: Fully qualified classname</p> <p>Default value: default implementation</p>
<code>http.protocol.allow-circular-redirects</code>	<p>Defines whether circular redirects (redirects to the same location) should be allowed. The HTTP spec is not sufficiently clear whether circular redirects are permitted, therefore optionally they can be enabled.</p> <p>Type: Boolean</p> <p>Default value: <undefined></p>
<code>http.protocol.content-charset</code>	<p>The charset to be used for encoding content body.</p> <p>Type: String</p> <p>Default value: ISO-8859-1</p>
<code>http.protocol.cookie-policy</code>	<p>The cookie policy to be used for cookie management.</p> <p>Type: String</p> <p>Default value: <code>CookiePolicy.RFC_2109</code></p>
<code>http.protocol.credential-charset</code>	<p>The charset to be used when encoding credentials. If not defined then the value of the http.protocol.element-charset should be used.</p> <p>Type: String</p> <p>Default value: <undefined></p>
<code>http.protocol.element-charset</code>	<p>The charset to be used for encoding/decoding HTTP protocol elements (status line and headers).</p> <p>Type: String</p> <p>Default value: US-ASCII</p>

HttpClient Parameters *(continued)*

Name	Description
<code>http.protocol.expect-continue</code>	<p>Activates “Expect: 100-Continue” handshake for the entity enclosing methods. The “Expect: 100-Continue” handshake allows a client that is sending a request message with a request body to determine if the origin server is willing to accept the request (based on the request headers) before the client sends the request body.</p> <p>The use of the “Expect: 100-continue” handshake can result in noticeable performance improvement for entity enclosing requests (such as POST and PUT) that require the target server’s authentication. “Expect: 100-continue” handshake should be used with caution, as it may cause problems with HTTP servers and proxies that do not support HTTP/1.1 protocol.</p> <p>Type: Boolean Default value: <undefined></p>
<code>http.protocol.head-body-timeout</code>	<p>Sets period of time in milliseconds to wait for a content body sent in response to HEAD response from a non-compliant server. If the parameter is not set or set to -1 non-compliant response body check is disabled.</p> <p>Type: Integer Default value: <undefined></p>
<code>http.protocol.max-redirects</code>	<p>Defines the maximum number of redirects to be followed. The limit on number of redirects is intended to prevent infinite loops.</p> <p>Type: Integer Default value: <undefined></p>
<code>http.protocol.reject-head-body</code>	<p>Defines whether the content body sent in response to HEAD request should be rejected.</p> <p>Type: Boolean Default value: <undefined></p>
<code>http.protocol.reject-relative-redirect</code>	<p>Defines whether relative redirects should be rejected.</p> <p>Type: Boolean Default value: <undefined></p>

HttpClient Parameters (*continued*)

Name	Description
<code>http.protocol.single-cookie-header</code>	<p>Defines whether cookies should be put on a single response header.</p> <p>Type: Boolean</p> <p>Default value: <undefined></p>
<code>http.protocol.status-line-garbage-limit</code>	<p>Defines the maximum number of ignorable lines before we expect a HTTP response's status code.</p> <p>With HTTP/1.1 persistent connections, the problem arises that broken scripts could return a wrong Content-Length (there are more bytes sent than specified). Unfortunately, in some cases, this is not possible after the bad response, but only before the next one. So, HttpClient must be able to skip those surplus lines this way. Set this to 0 to disallow any garbage/empty lines before the status line. To specify no limit, use <code>Integer.MAX_VALUE</code>.</p> <p>Type: Integer</p> <p>Default value: <undefined></p>
<code>http.protocol.strict-transfer-encoding</code>	<p>Defines whether responses with an invalid Transfer-Encoding header should be rejected.</p> <p>Type: Boolean</p> <p>Default value: <undefined></p>
<code>http.protocol.unambiguous-statusline</code>	<p>Defines whether HTTP methods should reject ambiguous HTTP status line.</p> <p>Type: Boolean</p> <p>Default value: <undefined></p>
<code>http.protocol.version</code>	<p>The HTTP protocol version used per default by the HTTP methods.</p> <p>Type: <code>HttpVersion</code></p> <p>Syntax: <(int)major>.<(int)minor>; e.g., 1.1</p> <p>Default value: <code>HttpVersion_1_1</code></p>

HttpClient Parameters *(continued)*

Name	Description
<code>http.protocol.warn-extra-input</code>	<p>Defines HttpClient's behavior when a response provides more bytes than expected (specified with Content-Length header, for example). Such surplus data makes the HTTP connection unreliable for keep-alive requests, as malicious response data (faked headers etc.) can lead to undesired results on the next request using that connection.</p> <p>If this parameter is set to true, any detection of extra input data will generate a warning in the log.</p> <p>Type: Boolean</p> <p>Default value: <undefined></p>
<code>http.socket.linger</code>	<p>The linger time (<code>SO_LINGER</code>) in seconds. This option disables/enables immediate return from a <code>close()</code> of a TCP Socket. Enabling this option with a non-zero Integer timeout means that a <code>close()</code> will block pending the transmission and acknowledgement of all data written to the peer, at which point the socket is closed gracefully. Value 0 implies that the option is disabled. Value -1 implies that the JRE default is used.</p> <p>Type: Integer</p> <p>Default value: <undefined></p>
<code>http.socket.receive-buffer</code>	<p>The value to set on <code>Socket.setReceiveBufferSize(int)</code>. This value is a suggestion to the kernel from the application about the size of buffers to use for the data to be received over the socket.</p> <p>Type: Integer</p> <p>Default value: <undefined></p>
<code>http.socket.sendbuffer</code>	<p>The value to set on <code>Socket.setSendBufferSize(int)</code>. This value is a suggestion to the kernel from the application about the size of buffers to use for the data to be sent over the socket.</p> <p>Type: Integer</p> <p>Default value: <undefined></p>

HttpClient Parameters *(continued)*

Name	Description
<code>http.socket.timeout</code>	<p>Sets the socket timeout (<code>SO_TIMEOUT</code>) in milliseconds to be used when executing the method. A timeout value of zero is interpreted as an infinite timeout.</p> <p>Type: Integer</p> <p>Default value: <undefined></p>
<code>http.socket.timeout</code>	<p>The default socket timeout (<code>SO_TIMEOUT</code>) in milliseconds which is the timeout for waiting for data. A timeout value of zero is interpreted as an infinite timeout. This value is used when no socket timeout is set in the HTTP method parameters.</p> <p>Type: Integer</p> <p>Default value: <undefined></p>
<code>http.tcp.nodelay</code>	<p>Determines whether Nagle's algorithm is to be used. The Nagle's algorithm tries to conserve bandwidth by minimizing the number of segments that are sent. When applications need to decrease network latency and increase performance, they can disable Nagle's algorithm (by enabling <code>TCP_NODELAY</code>). Data will be sent earlier, at the cost of an increase in bandwidth consumption.</p> <p>Type: Boolean</p> <p>Default value: <undefined></p>
<code>http.useragent</code>	<p>The content of the User-Agent header used by the HTTP methods.</p> <p>Type: String</p> <p>Default value: <Official release name> e.g., Jakarta Commons-HttpClient/3.0</p>

Index

A

- administrators
 - property that sets admin ACL 124
- application servers
 - properties 51
- authentication properties 52

B

- BlobServer
 - cache settings 58
 - properties 58
 - security setting 55

C

- cc.textdistinct 135
- cluster
 - properties 60
- content tables
 - properties 61, 64

D

- database
 - properties 65
- deleting
 - properties 12

- disk cache properties 82

E

- e-mail
 - properties 72
 - specifying which user attribute holds address 129
- Engage
 - properties 163

F

- firewall server
 - IP address 74
 - port number 75

H

- HTTP
 - properties 79

J

- Java Server Pages, *See* JSP
- JSP
 - properties 76

L

- logging, message
 - properties 140

M

message logging
properties 140

P

performance
ft.filecheck property 89
preferences
properties 114
properties
adding 11
administrator 124
application server 51
authentication 52
cluster 60
content table 61, 64
database 65
deleting 12
e-mail 72
Engage 163
HTTP 79
JSP 76
large text fields 67
message logging 140
preferences 114
publishing 74, 117
resultset caching 86, 92
Satellite Server 90
search engine 92
security 55
setting 10
URL columns 81
visitor data 158
Web Mode 125
Property Editor
adding properties 11
deleting properties 12
setting properties 10

publishing

properties 74, 117

R

resultset caching
properties 86, 92

S

Satellite Server
properties 90
search engines
properties 92
security
properties 55
sources
defined 74

T

targets
defined 74

U

URL columns
properties 81
user management
authentication properties 52

V

visitor data
properties 158

W

Web Mode
property 125

Index of Properties

advancedUI.enableAssetForms 133
afk.historydata 15
afk.publishdata 15
am.debug 110
analysisconnector.version 92
analytics.datacaptureurl 100
analytics.enabled 100
analytics.piurl 100
analytics.reporturl 100
analytics.user 100
appserverlink 152
asset.debug 110
baseDN 39
blocktimeout 146
bs.bCacheSize 58
bs.bCacheTimeout 58
bs.invalidheadernames 59
bs.security 55
bservice 148
cache_check_interval 144
cache_folder 144
cache_max 144
catalogcentre.version 92
cc.AssetTypeCSz 92
cc.attrDisplayStyle 134
cc.attributeinheritance 134
cc.bigint 65
cc.bigtext 65
cc.blob 65
cc.BlobServerCacheCSz 85
cc.BlobServerTimeout 84
cc.cacheNoSync 60
cc.cacheResults 87
cc.cacheResultsAbs 87
cc.cacheResultsTimeout 88

cc.CategoryCSz 93
cc.char 66
cc.ComparatorsKey 93
cc.contentkey 64
cc.datepicture 66
cc.datetime 66
cc.double 66
cc.ElementCatalogCSz 88
cc.ElementCatalogTimeout 88
cc.extrapath 134
cc.FiltersKey 93
cc.forcelower 66
cc.fullconstraint 134
cc.ignoreTblCase 67
cc.integer 67
cc.maxvarcharsize 67
cc.MimeTypeKey 93
cc.money 134
cc.null 67
cc.numeric 68
cc.PreviewgenKey 93
cc.primary 68
cc.queryablemaxvarcharlength 68
cc.querystyle 135
cc.rename 68
cc.security 55
cc.SiteCatalogCSz 88
cc.SiteCatalogTimeout 88
cc.smallint 68
cc.SourceKey 93
cc.StatusCodeCSz 93
cc.StatusCodeKey 93
cc.string 135
cc.stringpicture 69
cc.SystemACLCSz 88
cc.SystemACLTimeout 89
cc.SystemInfoCSz 89
cc.SystemInfoTimeout 89
cc.SystemPageCacheCSz 85
cc.SystemPageCacheTimeout 85
cc.SystemUsersCSz 89
cc.SystemUsersTimeout 89
cc.textdistinct 135
cc.unique 69
cc.url 135
cc.urlattrpath 135
cc.useLegacyInputNames 135
cc.varchar 69
ckeditor.showIncludedElementInSpan 132
className.Attribute 40
className.Attributes 40
className.IDir 40

className.IFactory 40
className.IName 40
className.IUserDir 41
className.JNDIName 41
cleandns 38
cn 36
com.fatwire.logging.cs 22
com.fatwire.logging.cs.auth 22
com.fatwire.logging.cs.blobserver 22
com.fatwire.logging.cs.cache.page 22
com.fatwire.logging.cs.cache.resultset 22
com.fatwire.logging.cs.core.http.HttpAccess 23
com.fatwire.logging.cs.core.uri.assembler 23
com.fatwire.logging.cs.core.uri.definition 23
com.fatwire.logging.cs.db 23
com.fatwire.logging.cs.errno 23
com.fatwire.logging.cs.event 24
com.fatwire.logging.cs.export 24
com.fatwire.logging.cs.filelock 24
com.fatwire.logging.cs.firstsite.filter 24
com.fatwire.logging.cs.install 24
com.fatwire.logging.cs.jsp 24
com.fatwire.logging.cs.realtime 25
com.fatwire.logging.cs.request 25
com.fatwire.logging.cs.satellite 25
com.fatwire.logging.cs.satellite.cache 25
com.fatwire.logging.cs.satellite.host 25
com.fatwire.logging.cs.satellite.request 25
com.fatwire.logging.cs.session 26
com.fatwire.logging.cs.sync 26
com.fatwire.logging.cs.sysinfo 26
com.fatwire.logging.cs.time 27
com.fatwire.logging.cs.visitor.object 27
com.fatwire.logging.cs.visitor.ruleset 27
com.fatwire.logging.cs.xcelerate.advantage.recommendation 27
com.fatwire.logging.cs.xcelerate.approval 28
com.fatwire.logging.cs.xcelerate.asset 28
com.fatwire.logging.cs.xcelerate.assetmaker 28
com.fatwire.logging.cs.xcelerate.publish 28
com.fatwire.logging.cs.xcelerate.template 28
com.fatwire.logging.cs.xml 28
com.fatwire.logging.ui.model 32
com.fatwire.logging.ui.phase 32
com.fatwire.search.asset 29
com.fatwire.search.lucene 33
commerceconnector.version 93
contentcentre.version 94
contentserver.installation.folder 149
cookieprefix 149
cs.alwaysusedisk 82
cs.approvalLockStriping 94
cs.barEqualsSlash 55

cs.binarypath 124
cs.charset 154
cs.charset 34
cs.charset 78
cs.childfoldercount 95
cs.contenttype 154
cs.contenttype 34
cs.contenttype 78
cs.contenttype.UTF-8 154
cs.contenttype.UTF-8 34
cs.cookievariables 61
cs.dataindatabase 61
cs.dbconnpicture 69
cs.dbencoding 95
cs.dbtype 69
cs.disksize 154
cs.disksize 34
cs.disksize 78
cs.documentation 78
cs.dsn 69
cs.emailaccount 72
cs.emailauthenticator 72
cs.emailcharset 72
cs.emailcontenttype 72
cs.emailhost 72
cs.emailpassword 73
cs.emailreturnto 73
cs.eventhost 51
cs.expireonly 82
cs.freezeCache 83
cs.HTTP_HOST 79
cs.HTTP_PROTOCOL 79
cs.httpvariables 61
cs.IItemlist 83
cs.invalMemWindow 95
cs.jspclear 76
cs.jsppath 76
cs.jsprefresh 76
cs.jspresponsewrapper 76
cs.jsproot 77
cs.jspwork 77
cs.manage.expired.blob.inventory 83
cs.manageACL 52
cs.manageproperty 52
cs.manageUser 52
cs.manageUserAccess 52
cs.manageUserSystem 53
cs.mirrorhttpversion 74
cs.mirrorpassword 74
cs.mirrorproxyserver 74
cs.mirrorproxyserverport 75
cs.mirrorrowsperpost 75

cs.mirrorthreads 75
cs.mirroruser 75
cs.nocache 84
cs.parentfoldercount 94
cs.PastramiEngine 90
cs.pgCacheTimeout 84
cs.pgexportfolder 75
cs.privpassword 69
cs.privuser 70
cs.recordBlobInventory 59
cs.recordBlobInventory 84
cs.requestfactory 95
cs.requiresessioncookies 84
cs.satellitehosts 61
cs.satellitepassword 62
cs.satelliteusers 62
cs.selfmodify 62
cs.session 55
cs.sitepreview 80
cs.ssovalidator 53
cs.timeout 56
cs.uniqueidpoolsize 56
cs.urlfilerollup 81
cs.use.short.jsp.names 77
cs.wrapper 56
cs.xmlfolder 81
cs.xmlHeader 81
cs.xmlHeaderAutoStream 62
debug 18
defaultGroupAttrs 46
defaultPeopleAttrs 46
defaultReaderACLs 46
expiration 145
file_size 145
forgotpassword 49
formation 151
ft.approot 62
ft.catalogmanager 63
ft.cgipath 51
ft.contentserver 63
ft.debugport 71
ft.filecheck 89
ft.servletoutputstream 95
ft.suppressPasswordNames 71
ft.suppressPasswords 71
ft.sync 60
ft.treemanager 63
ft.usedisksync 60
ft.version 56
globally_replace_contentserver 151
groupparent 39
host 148

http.authentication.preemptive 169
http.connection.stalecheck 169
http.connection.timeout 169
http.connection-manager.class 170
http.connection-manager.max-per-host 170
http.connection-manager.max-total 170
http.connection-manager.timeout 170
http.dateparser.patterns 171
http.default-headers 171
http.method.multipart.boundary 171
http.method.response.buffer.warnlimit 172
http.method.retry-handler 172
http.protocol.allow-circular-redirects 172
http.protocol.content-charset 172
http.protocol.cookie-policy 172
http.protocol.credential-charset 172
http.protocol.element-charset 172
http.protocol.expect-continue 173
http.protocol.head-body-timeout 173
http.protocol.max-redirects 173
http.protocol.reject-head-body 173
http.protocol.reject-relative-redirect 173
http.protocol.single-cookie-header 174
http.protocol.status-line-garbage-limit 174
http.protocol.strict-transfer-encoding 174
http.protocol.unambiguous-statusline 174
http.protocol.version 174
http.protocol.warn-extra-input 175
http.socket.linger 175
http.socket.receivebuffer 175
http.socket.sendbuffer 175
http.socket.timeout 176
http.socket.timeout 176
http.tcp.nodelay 176
http.useragent 176
image.time 96
java.naming.factory.initial 42
java.naming.security.authentication 42
jndi.baseURL 42
jndi.connectAsUser 42
jndi.custom 42
jndi.login 43
jndi.password 43
jndi.poolConnections 43
jndi.poolsize 43
log.Directory.messages 141
log.filterLevel 140
log.Logger.messages 141
log.transformer.messages 141
log.wmentconnector.messages 141
logging.file 31
logging.format 31

logging.interval 21
logging.maxlogsize 31
logging.per-client-log 31
logging.roll 32
logging.timestamp 32
loginattribute 36
marketingstudio.version 96
memberof 37
ms.enable 163
mwb.assetsetclass 135
mwb.cartclass 136
mwb.cartsetclass 136
mwb.cartsetdir 19
mwb.commercecontextclass 136
mwb.commerceengineclass 136
mwb.commerceuserclass 136
mwb.conservativedependencies 136
mwb.defaultattributes 137
mwb.externalattributes 137
mwb.path 137
mwb.promotioncutoff 137
mwb.searchdir 137
mwb.searchstateclass 137
mwb.segmentcutoff 138
newformaction 151
ntlogin.DefaultACL 53
ntlogin.DefaultReaderACL 53
ntlogin.DefaultReaderID 53
ntlogin.DefaultReaderPW 54
ntlogin.LogFile 54
ntlogin.Logging 54
objectclassGroup 46
objectclassPerson 47
org.apache.commons.logging.Log 21
org.apache.commons.logging.LogFactory 21
org.apache.http 29
org.apache.http.client 29
org.apache.http.headers 30
org.apache.http.impl.client 29
org.apache.http.impl.conn 29
org.apache.http.wire 30
page.time 96
password 146
password 36
path.BlobServer 155
path.CacheServer 155
path.CatalogManager 155
path.ContentServer 155
path.CookieServer 155
path.DispatchManager 155
path.PageDispatchServer 155
path.SatelliteServer 156

path.SeedDispatchServer 156
path.SyncSeedDispatchServer 156
path.to.futuretense.ini 149
path.TreeManager 156
peopleparent 39
port 148
propagatecache (futuretense.ini) 96
propagatecache (satellite.properties) 152
protocol 148
readtimeout 146
request.folder 18
requiredGroupAttrs 47
requiredPeopleAttrs 47
rsCacheOverinCache 96
satellite.blob.cachecontrol.default 90
satellite.page.cachecontrol.default 91
scratch.cleanup.schedule 152
search.returnLimit 48
search.scope 48
search.timeoutVal 48
secure.CatalogManager 56
secure.DebugServer 57
secure.TreeManager 57
security.checkpagelets 63
security.class 18
service 148
servlet 146
servlet-path 152
sessionid.cookie.prefix 150
sharesession 150
singlesignon 54
soap.binaryRowsType 97
soap.iList 97
soap.likeConstraint 97
soap.listRowsType 97
soap.nestedConstraint 97
soap.rangeConstraint 97
soap.richTextConstraint 97
soap.searchstate 98
soap.standardConstraint 98
soap.stringRowsType 98
soap.stringVarsType 98
soap.urlRowsType 98
soap.URLType 98
ss.flushall 85
syntax.beginquote 44
syntax.beginquote2 44
syntax.custom 43
syntax.direction 44
syntax.endquote 44
syntax.endquote2 44
syntax.escape 44

syntax.ignorecase 45
syntax.separator 45
syntax.separatorava 45
syntax.separatorypeval 45
syntax.trimblanks 45
thread.count 17
thread.growcache 17
thread.idle 17
thread.wait 17
transformer.imgdir 122
transformer.imgurl 123
transparent.content-type.pattern 146
uniquemember 36
uri.assembler.1.classname 156
uri.assembler.1.shortform 156
uri.assembler.2.classname 157
uri.assembler.2.shortform 157
uri.assembler.3.classname 157
uri.assembler.3.shortform 157
username 147
username 37
vis.adminrole 158
vis.compileclasspath 158
vis.editrole 158
vis.genclasspath 158
vis.money 159
vis.path 159
vis.rulesetxmlpath 159
vis.sessiondata 159
vis.update 159
vis.url 159
vis.urlpath 159
vis.useSessionVisitorConnection 160
wem.enabled 124
xcelelem.manageuserpub 113
xcelelem.publishfactors 113
xcelelem.publishoptions 113
xcelelem.setpubid 113
xcelerate.adminacl 124
xcelerate.adminrole 124
xcelerate.approval.dependency.chunksize 124
xcelerate.asset.shareToAllAllowed 101
xcelerate.asset.sizeofnamefield 101
xcelerate.authorizefunctions 104
xcelerate.base 125
xcelerate.batchhost 117
xcelerate.batchloadsizeonpublish 117
xcelerate.batchmode 117
xcelerate.batchpass 117
xcelerate.batchsavesizeonpublish 117
xcelerate.batchuser 118
xcelerate.blobref 118

xcelerate.body.length 101
xcelerate.bulkapprovechunk 118
xcelerate.charset 114
xcelerate.ckeditor.basepath 132
xcelerate.crosssiteassign 125
xcelerate.defaultacl 101
xcelerate.defaultbase 101
xcelerate.defaultcscacheinfo 102
xcelerate.defaultcsstatus 102
xcelerate.defaultlang 125
xcelerate.defaultpagecriteria 102
xcelerate.defaultpagecriteriaSiteEntry 102
xcelerate.defaultpreviewurlgenerator 125
xcelerate.defaultsscachefinfo 102
xcelerate.deny.abstainfromvoting 104
xcelerate.deny.approve 104
xcelerate.deny.authorize 104
xcelerate.deny.build 104
xcelerate.deny.checkout 104
xcelerate.deny.copy 104
xcelerate.deny.delegate 104
xcelerate.deny.delete 105
xcelerate.deny.edit 105
xcelerate.deny.inspect 105
xcelerate.deny.placepage 105
xcelerate.deny.preview 105
xcelerate.deny.removefromgroup 105
xcelerate.deny.removefromworkflow 105
xcelerate.deny.rollback 105
xcelerate.deny.setExportData 105
xcelerate.deny.setnestedworkflow 106
xcelerate.deny.setparticipants 106
xcelerate.deny.setprocessdeadline 106
xcelerate.deny.setstepdeadline 106
xcelerate.deny.share 106
xcelerate.deny.showparticipants 106
xcelerate.deny.showstatus 106
xcelerate.deny.showversion 107
xcelerate.displayablenameattr 129
xcelerate.domain 125
xcelerate.donotregenerate 119
xcelerate.editrole 125
xcelerate.emailattr 129
xcelerate.emailnotification 114
xcelerate.enableinsite 125
xcelerate.ewebeditpro 103
xcelerate.exportmaxfilename 119
xcelerate.grant.abstainfromvoting 107
xcelerate.grant.approve 107
xcelerate.grant.authorize 107
xcelerate.grant.build 107
xcelerate.grant.checkout 107

xcelerate.grant.copy 107
xcelerate.grant.delegate 107
xcelerate.grant.delete 108
xcelerate.grant.edit 108
xcelerate.grant.inspect 108
xcelerate.grant.placepage 108
xcelerate.grant.preview 108
xcelerate.grant.removefromgroup 108
xcelerate.grant.removefromworkflow 108
xcelerate.grant.rollback 108
xcelerate.grant.setExportData 108
xcelerate.grant.setnestedworkflow 108
xcelerate.grant.setparticipants 109
xcelerate.grant.setprocessdeadline 109
xcelerate.grant.setstepdeadline 109
xcelerate.grant.share 109
xcelerate.grant.showparticipants 109
xcelerate.grant.showstatus 109
xcelerate.grant.showversion 109
xcelerate.imageeditor.basepath 132
xcelerate.imageeditor.clarkii.basepath 132
xcelerate.imageurl 125
xcelerate.localeattr 129
xcelerate.locallanguagedir 111
xcelerate.lockdir 111
xcelerate.MaxLinks 103
xcelerate.mirrorini 119
xcelerate.objpubdir 111
xcelerate.pageref 119
xcelerate.presaveelt 120
xcelerate.previewhost 126
xcelerate.previewervlet 126
xcelerate.previewurlpagename 126
xcelerate.pubabortelt 120
xcelerate.pubcleanupelt 120
xcelerate.pubkeydir 111
xcelerate.publishallasettypes 120
xcelerate.publishinvalidate 120
xcelerate.publishquerystyle 126
xcelerate.pubrolesattr 129
xcelerate.pubsetupelt 121
xcelerate.remotecall 121
xcelerate.restrictSiteTree 114
xcelerate.rolemanagerclass 126
xcelerate.saveSearchdir 111
xcelerate.searchResultCols 127
xcelerate.seLimit 114
xcelerate.sePath 112
xcelerate.showSiteTree 115
xcelerate.sitenameattr 130
xcelerate.sitesattr 130
xcelerate.sitesroot 130

xcelerate.systemid 127
xcelerate.templatedefault 121
xcelerate.tempobjectsdir 112
xcelerate.thumbnaildir 112
xcelerate.transformpath 127
xcelerate.treehierassettype 115
xcelerate.treeMaxNodes 115
xcelerate.treetabmanagerclass 127
xcelerate.treeType 115
xcelerate.useDimensionAssets 132
xcelerate.userimageattr 131
xcelerate.usermanagerclass 128
xcelerate.usese 116
xcelerate.workflowdir 112
xcelerate.workflowengineclass 128

New Properties in Oracle WebCenter Sites 11gR1

advancedUI.enableAssetForms 133
cc.BlobServerCacheCSz 85
cc.BlobServerTimeout 84
com.fatwire.logging.cs.realtime 25
org.apache.http 29
org.apache.http.client 29
org.apache.http.headers 30
org.apache.http.impl.client 29
org.apache.http.impl.conn 29
org.apache.http.wire 30
xcelerate.imageeditor.clarkii.basepath 132

Deprecated Properties

analysisconnector.version 92
appserverlink 152
blocktimeout 146
cache_check_interval 144
catalogcentre.version 92
contentcentre.version 94
cs.httpvariables 61
cs.wrapper 56
ft.approot 62
ft.debugport 71
image.time 96
log.Directory.messages 141
log.filterLevel 140
log.Logger.messages 141
log.transformer.messages 141
log.wmentconnector.messages 141
logging.interval 21
page.time 96
readtimeout 146
satellite.page.cachecontrol.default 91
servlet-path 152
xcelelem.setpubid 113
xcelerate.emailnotification 114
xcelerate.ewebeditpro 103

